

globus gass copy

8.4

Generated by Doxygen 1.7.4

Tue May 1 2012 20:05:21

# Contents

<b>1</b>	<b>Main Page</b>	<b>2</b>
<b>2</b>	<b>Data Structure Index</b>	<b>2</b>
2.1	Data Structures . . . . .	2
<b>3</b>	<b>File Index</b>	<b>2</b>
3.1	File List . . . . .	2
<b>4</b>	<b>Data Structure Documentation</b>	<b>2</b>
4.1	globus_gass_copy_glob_stat_t Struct Reference . . . . .	2
4.1.1	Detailed Description . . . . .	3
4.1.2	Field Documentation . . . . .	3
4.2	globus_gass_copy_state_s Struct Reference . . . . .	3
4.2.1	Detailed Description . . . . .	4
4.2.2	Field Documentation . . . . .	4
4.3	globus_i_gass_copy_buffer_t Struct Reference . . . . .	4
4.3.1	Detailed Description . . . . .	4
4.4	globus_i_gass_copy_cancel_s Struct Reference . . . . .	4
4.4.1	Detailed Description . . . . .	4
4.5	globus_i_gass_copy_monitor_t Struct Reference . . . . .	4
4.5.1	Detailed Description . . . . .	5
4.6	globus_i_gass_copy_state_target_s Struct Reference . . . . .	5
4.6.1	Detailed Description . . . . .	5
4.6.2	Field Documentation . . . . .	5
<b>5</b>	<b>File Documentation</b>	<b>6</b>
5.1	globus_gass_copy.c File Reference . . . . .	6
5.1.1	Detailed Description . . . . .	7
5.1.2	Function Documentation . . . . .	7
5.2	globus_gass_copy.h File Reference . . . . .	18
5.2.1	Detailed Description . . . . .	19
5.2.2	Define Documentation . . . . .	19
5.2.3	Typedef Documentation . . . . .	19
5.2.4	Enumeration Type Documentation . . . . .	20
5.2.5	Function Documentation . . . . .	20

# 1 Main Page

The Globus GASS Copy library is motivated by the desire to provide a uniform interface to transfer files specified by different protocols. The goals in doing this are to:

- Provide a robust way to describe and apply file transfer properties for a variety of protocols. These include the standard HTTP, FTP and GSIFTP options. Some of the new file transfer capabilities in GSIFTP are parallel, striping, authentication and TCP buffer sizing.
- Provide a service to support nonblocking file transfer and handle asynchronous file and network events.
- Provide a simple and portable way to implement file transfers.

Any program that uses Globus GASS Copy functions must include "globus\_gass\_copy.h".

## 2 Data Structure Index

### 2.1 Data Structures

Here are the data structures with brief descriptions:

<b>globus_gass_copy_glob_stat_t (Glob expanded entry information )</b>	<b>2</b>
<b>globus_gass_copy_state_s (The state structure contains all that is required to perform a file transfer from a source to a destination )</b>	<b>3</b>
<b>globus_i_gass_copy_buffer_t (The buffer structure used for read/write queue entries )</b>	<b>4</b>
<b>globus_i_gass_copy_cancel_s (Gass copy cancel struct )</b>	<b>4</b>
<b>globus_i_gass_copy_monitor_t (The state monitor struct )</b>	<b>4</b>
<b>globus_i_gass_copy_state_target_s (GASS copy target (e.g )</b>	<b>5</b>

## 3 File Index

### 3.1 File List

Here is a list of all documented files with brief descriptions:

<b>globus_gass_copy.c (Globus GASS Copy library )</b>	<b>6</b>
<b>globus_gass_copy.h (Header file for the gass copy library )</b>	<b>18</b>

## 4 Data Structure Documentation

### 4.1 globus\_gass\_copy\_glob\_stat\_t Struct Reference

Glob expanded entry information.

## Data Fields

- **globus\_gass\_copy\_glob\_entry\_t** type
- char \* **unique\_id**
- char \* **symlink\_target**
- int **mode**
- int **mdtm**
- globus\_off\_t **size**

### 4.1.1 Detailed Description

Glob expanded entry information.

### 4.1.2 Field Documentation

#### 4.1.2.1 **globus\_gass\_copy\_glob\_entry\_t globus\_gass\_copy\_glob\_stat\_t::type**

The file type of the entry.

#### 4.1.2.2 **char\* globus\_gass\_copy\_glob\_stat\_t::unique\_id**

A string that uniquely identifies the data that the entry refers to.

A file and a symlink to that file will have the same `unique_id`. It is NULL for when not available.

#### 4.1.2.3 **char\* globus\_gass\_copy\_glob\_stat\_t::symlink\_target**

This points to the full path of the target of a symlink.

It is NULL for non-symlinks or when not available.

#### 4.1.2.4 **int globus\_gass\_copy\_glob\_stat\_t::mode**

An integer specifying the mode of the file.

It is set to -1 when not available.

#### 4.1.2.5 **int globus\_gass\_copy\_glob\_stat\_t::mdtm**

An integer specifying the modification time of the file.

It is set to -1 when not available.

#### 4.1.2.6 **globus\_off\_t globus\_gass\_copy\_glob\_stat\_t::size**

A `globus_off_t` specifying the size of the file.

It is set to -1 when not available.

## 4.2 **globus\_gass\_copy\_state\_s** Struct Reference

The state structure contains all that is required to perform a file transfer from a source to a destination.

## Data Fields

- **globus\_i\_gass\_copy\_target\_t** **source**

- **globus\_i\_gass\_copy\_target\_t dest**
- **globus\_i\_gass\_copy\_monitor\_t monitor**
- globus\_mutex\_t **mutex**
- globus\_i\_gass\_copy\_cancel\_status\_t **cancel**

#### 4.2.1 Detailed Description

The state structure contains all that is required to perform a file transfer from a source to a destination.

#### 4.2.2 Field Documentation

##### 4.2.2.1 globus\_i\_gass\_copy\_target\_t globus\_gass\_copy\_state\_s::source

Source information for the file transfer.

##### 4.2.2.2 globus\_i\_gass\_copy\_target\_t globus\_gass\_copy\_state\_s::dest

Dest information for the file transfer.

##### 4.2.2.3 globus\_i\_gass\_copy\_monitor\_t globus\_gass\_copy\_state\_s::monitor

Used for signalling from the various callback functions.

##### 4.2.2.4 globus\_mutex\_t globus\_gass\_copy\_state\_s::mutex

coordinates the modifying of the state, aside from the target structures

##### 4.2.2.5 globus\_i\_gass\_copy\_cancel\_status\_t globus\_gass\_copy\_state\_s::cancel

indicates the status of the cancel operation.

### 4.3 globus\_i\_gass\_copy\_buffer\_t Struct Reference

The buffer structure used for read/write queue entries.

#### 4.3.1 Detailed Description

The buffer structure used for read/write queue entries.

### 4.4 globus\_i\_gass\_copy\_cancel\_s Struct Reference

gass copy cancel struct

#### 4.4.1 Detailed Description

gass copy cancel struct

### 4.5 globus\_i\_gass\_copy\_monitor\_t Struct Reference

The state monitor struct.

#### 4.5.1 Detailed Description

The state monitor struct.

### 4.6 globus\_i\_gass\_copy\_state\_target\_s Struct Reference

GASS copy target (e.g.

#### Data Fields

- char \* **url**
- globus\_gass\_copy\_attr\_t \* **attr**
- globus\_mutex\_t **mutex**
- globus\_fifo\_t **queue**
- int **n\_pending**
- int **n\_simultaneous**
- int **n\_complete**
- globus\_i\_gass\_copy\_target\_status\_t **status**
- globus\_gass\_copy\_url\_mode\_t **mode**
- globus\_gass\_transfer\_request\_t **request**
- globus\_bool\_t **free\_handle**
- globus\_bool\_t **seekable**

#### 4.6.1 Detailed Description

GASS copy target (e.g.

source, destination) transfer information.

#### 4.6.2 Field Documentation

##### 4.6.2.1 char\* globus\_i\_gass\_copy\_state\_target\_s::url

url for file transfer

##### 4.6.2.2 globus\_gass\_copy\_attr\_t\* globus\_i\_gass\_copy\_state\_target\_s::attr

attributes to control file transfer

##### 4.6.2.3 globus\_mutex\_t globus\_i\_gass\_copy\_state\_target\_s::mutex

coordinates the modifying of the target structure

##### 4.6.2.4 globus\_fifo\_t globus\_i\_gass\_copy\_state\_target\_s::queue

a queue to manage the reading/writing of data buffers

##### 4.6.2.5 int globus\_i\_gass\_copy\_state\_target\_s::n\_pending

Used for keeping track of reads/writes in the read/write queue.

##### 4.6.2.6 int globus\_i\_gass\_copy\_state\_target\_s::n\_simultaneous

Used to limit the number of n\_pending.

#### 4.6.2.7 `int globus_i_gass_copy_state_target_s::n_complete`

Used to compute the offset for ftp writes.

#### 4.6.2.8 `globus_i_gass_copy_target_status_t globus_i_gass_copy_state_target_s::status`

signifies the target has been successfully setup

#### 4.6.2.9 `globus_gass_copy_url_mode_t globus_i_gass_copy_state_target_s::mode`

mode used to identify the below target union struct.

#### 4.6.2.10 `globus_gass_transfer_request_t globus_i_gass_copy_state_target_s::request`

GASS equivalent of a handle.

#### 4.6.2.11 `globus_bool_t globus_i_gass_copy_state_target_s::free_handle`

If the IO handle was passed as an argument then FALSE If the IO handle was created internally then TRUE.

#### 4.6.2.12 `globus_bool_t globus_i_gass_copy_state_target_s::seekable`

Can `globus_io_file_seek()` be performed on this handle?

## 5 File Documentation

### 5.1 `globus_gass_copy.c` File Reference

Globus GASS Copy library.

#### Functions

- `globus_result_t globus_gass_copy_handle_init` (`globus_gass_copy_handle_t *handle`, `globus_gass_copy_handleattr_t *attr`)
- `globus_result_t globus_gass_copy_handle_destroy` (`globus_gass_copy_handle_t *handle`)
- `globus_result_t globus_gass_copy_set_buffer_length` (`globus_gass_copy_handle_t *handle`, `int length`)
- `globus_result_t globus_gass_copy_get_buffer_length` (`globus_gass_copy_handle_t *handle`, `int *length`)
- `globus_result_t globus_gass_copy_set_no_third_party_transfers` (`globus_gass_copy_handle_t *handle`, `globus_bool_t no_third_party_transfers`)
- `globus_result_t globus_gass_copy_get_no_third_party_transfers` (`globus_gass_copy_handle_t *handle`, `globus_bool_t *no_third_party_transfers`)
- `globus_result_t globus_gass_copy_set_allocate` (`globus_gass_copy_handle_t *handle`, `globus_bool_t send_allo`)
- `globus_result_t globus_gass_copy_set_stat_on_expand` (`globus_gass_copy_handle_t *handle`, `globus_bool_t always_stat`)
- `globus_result_t globus_gass_copy_set_partial_offsets` (`globus_gass_copy_handle_t *handle`, `globus_off_t offset`, `globus_off_t end_offset`)
- `globus_result_t globus_gass_copy_get_partial_offsets` (`globus_gass_copy_handle_t *handle`, `globus_off_t *offset`, `globus_off_t *end_offset`)
- `globus_result_t globus_gass_copy_attr_init` (`globus_gass_copy_attr_t *attr`)
- `globus_result_t globus_gass_copy_attr_set_ftp` (`globus_gass_copy_attr_t *attr`, `globus_ftp_client_operationattr_t *ftp_attr`)
- `globus_result_t globus_gass_copy_attr_set_io` (`globus_gass_copy_attr_t *attr`, `globus_io_attr_t *io_attr`)

- globus\_result\_t **globus\_gass\_copy\_attr\_set\_gass** (globus\_gass\_copy\_attr\_t \*attr, globus\_gass\_transfer\_requestattr\_t \*gass\_attr)
- globus\_result\_t **globus\_gass\_copy\_get\_url\_mode** (char \*url, globus\_gass\_copy\_url\_mode\_t \*mode)
- globus\_result\_t **globus\_gass\_copy\_register\_performance\_cb** (globus\_gass\_copy\_handle\_t \*handle, **globus\_gass\_copy\_performance\_cb\_t** callback, void \*user\_arg)
- globus\_result\_t **globus\_gass\_copy\_get\_status** (globus\_gass\_copy\_handle\_t \*handle, globus\_gass\_copy\_status\_t \*status)
- const char \* **globus\_gass\_copy\_get\_status\_string** (globus\_gass\_copy\_handle\_t \*handle)
- globus\_result\_t **globus\_gass\_copy\_url\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr)
- globus\_result\_t **globus\_gass\_copy\_url\_to\_handle** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, globus\_io\_handle\_t \*dest\_handle)
- globus\_result\_t **globus\_gass\_copy\_handle\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, globus\_io\_handle\_t \*source\_handle, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr)
- globus\_result\_t **globus\_gass\_copy\_register\_url\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr, globus\_gass\_copy\_callback\_t callback\_func, void \*callback\_arg)
- globus\_result\_t **globus\_gass\_copy\_register\_url\_to\_handle** (globus\_gass\_copy\_handle\_t \*handle, char \*source\_url, globus\_gass\_copy\_attr\_t \*source\_attr, globus\_io\_handle\_t \*dest\_handle, globus\_gass\_copy\_callback\_t callback\_func, void \*callback\_arg)
- globus\_result\_t **globus\_gass\_copy\_register\_handle\_to\_url** (globus\_gass\_copy\_handle\_t \*handle, globus\_io\_handle\_t \*source\_handle, char \*dest\_url, globus\_gass\_copy\_attr\_t \*dest\_attr, globus\_gass\_copy\_callback\_t callback\_func, void \*callback\_arg)
- globus\_result\_t **globus\_gass\_copy\_cache\_url\_state** (globus\_gass\_copy\_handle\_t \*handle, char \*url)
- globus\_result\_t **globus\_gass\_copy\_flush\_url\_state** (globus\_gass\_copy\_handle\_t \*handle, char \*url)
- globus\_result\_t **globus\_gass\_copy\_set\_user\_pointer** (globus\_gass\_copy\_handle\_t \*handle, void \*user\_pointer)
- globus\_result\_t **globus\_gass\_copy\_get\_user\_pointer** (globus\_gass\_copy\_handle\_t \*handle, void \*\*user\_data)
- globus\_result\_t **globus\_gass\_copy\_cancel** (globus\_gass\_copy\_handle\_t \*handle, globus\_gass\_copy\_callback\_t cancel\_callback, void \*cancel\_callback\_arg)
- globus\_result\_t **globus\_i\_gass\_copy\_target\_cancel** (**globus\_i\_gass\_copy\_cancel\_t** \*cancel\_info)

### 5.1.1 Detailed Description

Globus GASS Copy library.

#### See also

See the detailed description in **globus\_gass\_copy.h** (p. 18)

### 5.1.2 Function Documentation

#### 5.1.2.1 globus\_result\_t globus\_gass\_copy\_handle\_init ( globus\_gass\_copy\_handle\_t \* handle, globus\_gass\_copy\_handleattr\_t \* attr )

Initialize a GASS Copy handle.

A globus\_gass\_copy\_handle must be initialized before any transfers may be associated with it. This function initializes a globus\_gass\_copy\_handle to be used for doing transfers, this includes initializing a globus\_ftp\_client\_handle which will be used for doing any ftp/gsiftp transfers. The same handle may be used to perform multiple, consecutive transfers. However, there can only be one transfer associated with a particular handle at any given time. After all transfers to be associated with this handle have completed, the handle should be destroyed by calling **globus\_gass\_copy\_handle\_destroy()** (p. 8).



## Parameters

<i>handle</i>	The handle to be initialized
<i>attr</i>	The handle attributes used to use with this handle

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See also

**globus\_gass\_copy\_handle\_destroy()** (p. 8) , globus\_gass\_copy\_handleattr\_init(), globus\_ftp\_client\_handle\_init()

References GLOBUS\_GASS\_COPY\_MODULE.

### 5.1.2.2 globus\_result\_t globus\_gass\_copy\_handle\_destroy ( globus\_gass\_copy\_handle\_t \* *handle* )

Destroy a GASS Copy handle.

Destroy a gass\_copy\_handle, which was initialized using **globus\_gass\_copy\_handle\_init()** (p. 7), that will no longer be used for doing transfers. Once the handle is destroyed, no further transfers should be associated with it.

## Parameters

<i>handle</i>	The handle to be destroyed
---------------	----------------------------

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See also

**globus\_gass\_copy\_handle\_init()** (p. 7), globus\_ftp\_client\_handle\_destroy()

References GLOBUS\_GASS\_COPY\_MODULE.

### 5.1.2.3 globus\_result\_t globus\_gass\_copy\_set\_buffer\_length ( globus\_gass\_copy\_handle\_t \* *handle*, int *length* )

Set the size of the buffer to be used for doing transfers.

This function allows the user to set the size of the buffer that will be used for doing transfers, if this function is not called the buffer size will default to 1M.

## Parameters

<i>handle</i>	Set the buffer length for transfers associated with this handle.
<i>length</i>	The length, in bytes, to make the buffer.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

### 5.1.2.4 globus\_result\_t globus\_gass\_copy\_get\_buffer\_length ( globus\_gass\_copy\_handle\_t \* *handle*, int \* *length* )

Get the size of the buffer being used for doing transfers.

This function allows the user to get the size of the buffer that is being used for doing transfers.

## Parameters

<i>handle</i>	Get the buffer length for transfers associated with this handle.
<i>length</i>	The length, in bytes, of the buffer.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.5** globus\_result\_t globus\_gass\_copy\_set\_no\_third\_party\_transfers ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t *no\_third\_party\_transfers* )

Turn third-party transfers on or off.

(They are on by default.)

This function allows the user to turn third-party transfers on or off for ftp to ftp transfers associated with a particular handle. This is often desired if one of the servers involved in the transfer does not allow third-party transfers.

## Parameters

<i>handle</i>	Turn third-party transfers on or off for transfers associated with this handle. They are on by default.
<i>no_third_party_transfers</i>	GLOBUS_FALSE if third-party transfers should be used. GLOBUS_TRUE if third-party transfers should not be used.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References globus\_gass\_copy\_get\_status(), and GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.6** globus\_result\_t globus\_gass\_copy\_get\_no\_third\_party\_transfers ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t \* *no\_third\_party\_transfers* )

See if third-party transfers are turned on or off.

(They are on by default.)

This function allows the user to see if third-party transfers are turned on or off for ftp to ftp transfers associated with a particular handle. This is often desired if one of the servers involved in the transfer does not allow third-party transfers.

## Parameters

<i>handle</i>	See if third-party transfers are turned on or off for transfers associated with this handle. They are on by default.
<i>no_third_party_transfers</i>	GLOBUS_FALSE if third-party transfers should be used. GLOBUS_TRUE if third-party transfers should not be used.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.7** globus\_result\_t globus\_gass\_copy\_set\_allocate ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_bool\_t *send\_allo* )

Set allo on or off.

5.1.2.8 `globus_result_t globus_gass_copy_set_stat_on_expand ( globus_gass_copy_handle_t * handle, globus_bool_t always_stat )`

Make `globus_gass_copy_expand_url()` always send stat info.

5.1.2.9 `globus_result_t globus_gass_copy_set_partial_offsets ( globus_gass_copy_handle_t * handle, globus_off_t offset, globus_off_t end_offset )`

Set the offsets to be used for doing partial transfers.

This function allows the user to set the offsets that will be used for doing partial transfers. An offset of -1 will disable partial transfers. An `end_offset` of -1 means EOF.

#### Parameters

<i>handle</i>	Set the offsets for partial transfers associated with this handle.
<i>offset</i>	The starting offset for the partial transfer.
<i>end_offset</i>	The ending offset for the partial transfer.

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

References `GLOBUS_GASS_COPY_MODULE`.

5.1.2.10 `globus_result_t globus_gass_copy_get_partial_offsets ( globus_gass_copy_handle_t * handle, globus_off_t * offset, globus_off_t * end_offset )`

Get the offsets being used for doing partial transfers.

This function allows the user to get the offsets that are being used for doing partial transfers. An offset of -1 means partial transfers are disabled.

#### Parameters

<i>handle</i>	Get the offsets for partial transfers associated with this handle.
<i>offset</i>	The starting offset for the partial transfer.
<i>end_offset</i>	The ending offset for the partial transfer.

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

References `GLOBUS_GASS_COPY_MODULE`.

5.1.2.11 `globus_result_t globus_gass_copy_attr_init ( globus_gass_copy_attr_t * attr )`

Initialize an attribute structure.

The `globus_gass_copy_attr_t` can be used to pass the `globus_gass_copy` library information about how a transfer should be performed. It must first be initialized by calling this function. Then any or all of the following functions may be called to set attributes associated with a particular protocol: **`globus_gass_copy_attr_set_ftp()`** (p. 11), **`globus_gass_copy_attr_set_gass()`** (p. 12), **`globus_gass_copy_attr_set_io()`** (p. 11). Any function which takes a `globus_gass_copy_attr_t` as an argument will also accept `GLOBUS_NULL`, in which case the appropriate set of default attributes will be used.

#### Parameters

<i>attr</i>	The attribute structure to be initialized
-------------	---

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See also

**globus\_gass\_copy\_attr\_set\_ftp()** (p. 11), **globus\_gass\_copy\_attr\_set\_gass()** (p. 12), **globus\_gass\_copy\_attr\_set\_io()** (p. 11), **globus\_gass\_copy\_get\_url\_mode()** (p. 12).

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.12 **globus\_result\_t globus\_gass\_copy\_attr\_set\_ftp ( globus\_gass\_copy\_attr\_t \* attr, globus\_ftp\_client\_operationattr\_t \* ftp\_attr )**

Set the attributes for ftp/gsiftp transfers.

In order to specify attributes for ftp/gsiftp transfers, a globus\_ftp\_client\_operationattr\_t should be initialized and its values set using the appropriate globus\_ftp\_client\_operationattr\_\* functions. The globus\_ftp\_client\_operationattr\_t \* can then be passed to the globus\_gass\_copy\_attr\_t via this function.

## Parameters

<i>attr</i>	A globus_gass_copy attribute structure
<i>ftp_attr</i>	The ftp/gsiftp attributes to be used

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See also

**globus\_gass\_copy\_attr\_init()** (p. 10), **globus\_gass\_copy\_attr\_set\_gass()** (p. 12), **globus\_gass\_copy\_attr\_set\_io()** (p. 11), **globus\_gass\_copy\_get\_url\_mode()** (p. 12), **globus\_ftp\_client\_operationattr\_\***

References GLOBUS\_GASS\_COPY\_MODULE.

5.1.2.13 **globus\_result\_t globus\_gass\_copy\_attr\_set\_io ( globus\_gass\_copy\_attr\_t \* attr, globus\_io\_attr\_t \* io\_attr )**

Set the attributes for file transfers.

In order to specify attributes for file transfers, a globus\_io\_attr\_t should be initialized and its values set using the appropriate globus\_io\_attr\_\* functions. The globus\_io\_attr\_t can then be passed to the globus\_gass\_copy\_attr\_t via this function.

## Parameters

<i>attr</i>	A globus_gass_copy attribute structure
<i>io_attr</i>	The file attributes to be used

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

## See also

**globus\_gass\_copy\_attr\_init()** (p. 10), **globus\_gass\_copy\_attr\_set\_gass()** (p. 12), **globus\_gass\_copy\_attr\_set\_ftp()** (p. 11), **globus\_gass\_copy\_get\_url\_mode()** (p. 12), **globus\_io\_attr\_\***

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.14** `globus_result_t globus_gass_copy_attr_set_gass ( globus_gass_copy_attr_t * attr, globus_gass_transfer_requestattr_t * gass_attr )`

Set the attributes for http/https transfers.

In order to specify attributes for http/https transfers, a `globus_gass_transfer_requestattr_t` should be initialized and its values set using the appropriate `globus_gass_transfer_requestattr_*` functions. The `globus_gass_transfer_requestattr_t` can then be passed to the `globus_gass_copy_attr_t` via this function.

#### Parameters

<i>attr</i>	A <code>globus_gass_copy</code> attribute structure
<i>gass_attr</i>	The http/https attributes to be used

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

#### See also

**`globus_gass_copy_attr_init()`** (p. 10), **`globus_gass_copy_attr_set_io()`** (p. 11), **`globus_gass_copy_attr_set_ftp()`** (p. 11), **`globus_gass_copy_get_url_mode()`** (p. 12), `globus_gass_transfer_requestattr_*`

References `GLOBUS_GASS_COPY_MODULE`.

**5.1.2.15** `globus_result_t globus_gass_copy_get_url_mode ( char * url, globus_gass_copy_url_mode_t * mode )`

Classify the URL schema into the transfer method that will be used to do the actual tranfer.

This function enables the user to determine what protocol will be used to transfer data to/from a particular url. This information can then be used to specify the appropriate attributes when initiating a transfer.

#### Parameters

<i>url</i>	The URL for schema checking
<i>mode</i>	the filled in schema type of the URL param

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

#### See also

**`globus_gass_copy_attr_init()`** (p. 10), **`globus_gass_copy_attr_set_io()`** (p. 11), **`globus_gass_copy_attr_set_ftp()`** (p. 11), `globus_gass_copy_set_gass()`

References `GLOBUS_GASS_COPY_MODULE`.

**5.1.2.16** `globus_result_t globus_gass_copy_register_performance_cb ( globus_gass_copy_handle_t * handle, globus_gass_copy_performance_cb_t callback, void * user_arg )`

Register a performance information callback.

Use this to register a performance information callback. You change or set to `GLOBUS_NULL` the callback any time a transfer is not occurring.

#### Parameters

<i>handle</i>	an initialized gass copy handle for which you would like to see performance info
<i>callback</i>	the performance callback
<i>user_arg</i>	a user pointer that will be passed to all callbacks for a given handle

## Returns

- GLOBUS\_SUCCESS
- error on a NULL or busy handle

## See also

**globus\_gass\_copy\_performance\_cb\_t** (p. 19)

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.17 globus\_result\_t globus\_gass\_copy\_get\_status ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_gass\_copy\_status\_t \* *status* )**

Get the status code of the current transfer.

Get the status of the last transfer to be initiated using the given handle. Only one transfer can be active on a handle at a given time, therefore new transfers may only be initiated when the current status is one of the following: GLOBUS\_GASS\_COPY\_STATUS\_NONE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_SUCCESS, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_FAILURE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_CANCELLED

## Parameters

<i>handle</i>	A globus_gass_copy_handle
<i>status</i>	Will be one of the following: GLOBUS_GASS_COPY_STATUS_NONE (No transfers have been initiated using this handle.) GLOBUS_GASS_COPY_STATUS_PENDING (A transfer is currently being set up.) GLOBUS_GASS_COPY_STATUS_TRANSFER_IN_PROGRESS (There is currently a transfer in progress.) GLOBUS_GASS_COPY_STATUS_CANCEL (The last transfer initiated using this handle has been cancelled by the user before completing, and is in the process of being cleaned up.) GLOBUS_GASS_COPY_STATUS_FAILURE (The last transfer initiated using this handle failed, and is in the process of being cleaned up.) GLOBUS_GASS_COPY_STATUS_DONE_SUCCESS (The last transfer initiated using this handle has completed successfully.) GLOBUS_GASS_COPY_STATUS_DONE_FAILURE (The last transfer initiated using this handle failed and has finished cleaning up.) GLOBUS_GASS_COPY_STATUS_DONE_CANCELLED (The last transfer initiated using this handle was cancelled and has finished cleaning up.)

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.18 const char\* globus\_gass\_copy\_get\_status\_string ( globus\_gass\_copy\_handle\_t \* *handle* )**

Get the status string of the current transfer.

Get the status of the last transfer to be initiated using the given handle. Only one transfer can be active on a handle at a given time, therefore new transfers may only be initiated when the current status is one of the following: GLOBUS\_GASS\_COPY\_STATUS\_NONE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_SUCCESS, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_FAILURE, GLOBUS\_GASS\_COPY\_STATUS\_DONE\_CANCELLED

## Parameters

<i>handle</i>	A globus_gass_copy_handle
---------------	---------------------------

## Returns

Returns a pointer to a character string describing the current status

References globus\_gass\_copy\_get\_status().

5.1.2.19 `globus_result_t globus_gass_copy_url_to_url ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, char * dest_url, globus_gass_copy_attr_t * dest_attr )`

Transfer data from source URL to destination URL (blocking)

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer from the source should be done
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<code>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</code>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<code>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</code>	next error description

#### See also

`globus_gass_copy_url_to_handle()` (p. 14) `globus_gass_copy_handle_to_url()` (p. 15)

References GLOBUS\_GASS\_COPY\_MODULE, and `globus_gass_copy_register_url_to_url()`.

5.1.2.20 `globus_result_t globus_gass_copy_url_to_handle ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, globus_io_handle_t * dest_handle )`

Transfer data from source URL to an IO handle (blocking)

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer from the source should be done
<i>dest_handle</i>	transfer data to this IO handle

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<code>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</code>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<code>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</code>	next error description

#### See also

`globus_gass_copy_url_to_url()` (p. 14) `globus_gass_copy_handle_to_url()` (p. 15)

References GLOBUS\_GASS\_COPY\_MODULE, and globus\_gass\_copy\_register\_url\_to\_handle().

5.1.2.21 `globus_result_t globus_gass_copy_handle_to_url ( globus_gass_copy_handle_t * handle, globus_io_handle_t * source_handle, char * dest_url, globus_gass_copy_attr_t * dest_attr )`

Transfer data from an IO handle to destination URL (blocking)

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_handle</i>	transfer data from this IO handle
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was completed successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<code>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</code>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<code>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</code>	next error description

#### See also

**globus\_gass\_copy\_url\_to\_url()** (p. 14) **globus\_gass\_copy\_url\_to\_handle()** (p. 14)

References GLOBUS\_GASS\_COPY\_MODULE, and globus\_gass\_copy\_register\_handle\_to\_url().

5.1.2.22 `globus_result_t globus_gass_copy_register_url_to_url ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, char * dest_url, globus_gass_copy_attr_t * dest_attr, globus_gass_copy_callback_t callback_func, void * callback_arg )`

Transfer data from source URL to destination URL (non-blocking)

This functions initiates a transfer from source URL to destination URL, then returns immediately.

When the transfer is completed or if the transfer is aborted, the `callback_func` will be invoked with the final status of the transfer.

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer form the source should be done
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done
<i>callback_func</i>	Callback to be invoked once the transfer is completed.
<i>callback_arg</i>	Argument to be passed to the <code>callback_func</code> .

#### Returns

This function returns GLOBUS\_SUCCESS if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:



## Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description

## See also

**globus\_gass\_copy\_register\_url\_to\_handle()** (p. 16), **globus\_gass\_copy\_register\_handle\_to\_url()** (p. 16)

References `globus_i_gass_copy_state_target_s::attr`, `globus_gass_copy_state_s::cancel`, `globus_gass_copy_state_s::dest`, `globus_gass_copy_get_url_mode()`, `GLOBUS_GASS_COPY_MODULE`, and `globus_gass_copy_state_s::source`.

5.1.2.23 `globus_result_t globus_gass_copy_register_url_to_handle ( globus_gass_copy_handle_t * handle, char * source_url, globus_gass_copy_attr_t * source_attr, globus_io_handle_t * dest_handle, globus_gass_copy_callback_t callback_func, void * callback_arg )`

Transfer data from source URL to an IO handle (non-blocking)

This functions initiates a transfer from source URL to an IO handle, then returns immediately.

When the transfer is completed or if the transfer is aborted, the `callback_func` will be invoked with the final status of the transfer.

## Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_url</i>	transfer data from this URL
<i>source_attr</i>	Attributes describing how the transfer form the source should be done
<i>dest_handle</i>	transfer data to this IO handle
<i>callback_func</i>	Callback to be invoked once the transfer is completed.
<i>callback_arg</i>	Argument to be passed to the <code>callback_func</code> .

## Returns

This function returns `GLOBUS_SUCCESS` if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

## Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to GLOBUS_NULL, so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description

## See also

**globus\_gass\_copy\_register\_url\_to\_url()** (p. 15), **globus\_gass\_copy\_register\_handle\_to\_url()** (p. 16)

References `globus_gass_copy_state_s::cancel`, `globus_gass_copy_state_s::dest`, `globus_gass_copy_get_url_mode()`, `GLOBUS_GASS_COPY_MODULE`, and `globus_gass_copy_state_s::source`.

5.1.2.24 `globus_result_t globus_gass_copy_register_handle_to_url ( globus_gass_copy_handle_t * handle, globus_io_handle_t * source_handle, char * dest_url, globus_gass_copy_attr_t * dest_attr, globus_gass_copy_callback_t callback_func, void * callback_arg )`

Transfer data from an IO handle to destination URL (non-blocking)

This functions initiates a transfer from an IO handle to destination URL, then returns immediately.

When the transfer is completed or if the transfer is aborted, the `callback_func` will be invoked with the final status of the transfer.

#### Parameters

<i>handle</i>	The handle to perform the copy operation
<i>source_handle</i>	transfer data from this IO handle
<i>dest_url</i>	transfer data to this URL
<i>dest_attr</i>	Attributes describing how the transfer to the destination should be done
<i>callback_func</i>	Callback to be invoked once the transfer is completed.
<i>callback_arg</i>	Argument to be passed to the <code>callback_func</code> .

#### Returns

This function returns `GLOBUS_SUCCESS` if the transfer was initiated successfully, or a result pointing to an object of one of the the following error types:

#### Return values

<i>GLOBUS_GASS_COPY_ERROR_TYPE_NULL_PARAMETER</i>	The handle was equal to <code>GLOBUS_NULL</code> , so the transfer could not processed.
<i>GLOBUS_GASS_COPY_ERROR_TYPE_next_error</i>	next error description

#### See also

**`globus_gass_copy_register_url_to_url()`** (p. 15), **`globus_gass_copy_register_url_to_handle()`** (p. 16)

References `globus_gass_copy_state_s::cancel`, `globus_gass_copy_state_s::dest`, `globus_gass_copy_get_url_mode()`, `GLOBUS_GASS_COPY_MODULE`, and `globus_gass_copy_state_s::source`.

5.1.2.25 `globus_result_t globus_gass_copy_cache_url_state ( globus_gass_copy_handle_t * handle, char * url )`

Cache connections to an FTP or GSIFTP server.

Explicitly cache connections to URL server. When an URL is cached, the connection to the URL server will not be closed after a file transfer completes.

#### Parameters

<i>handle</i>	Handle which will contain a cached connection to the URL server.
<i>url</i>	The URL of the FTP or GSIFTP server to cache.

#### Returns

This function returns `GLOBUS_SUCCESS` if successful, or a `globus_result_t` indicating the error that occurred.

References `GLOBUS_GASS_COPY_MODULE`.

5.1.2.26 `globus_result_t globus_gass_copy_flush_url_state ( globus_gass_copy_handle_t * handle, char * url )`

Remove a cached connection to an FTP or GSIFTP server.

Explicitly remove a cached connection to an FTP or GSIFTP server. If an idle connection to an FTP server exists, it will be closed.

#### Parameters

---

<i>handle</i>	Handle which contains a cached connection to the URL server.
<i>url</i>	The URL of the FTP or GSIFTP server to remove.

## Returns

This function returns GLOBUS\_SUCCESS if successful, or a globus\_result\_t indicating the error that occurred.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.27** globus\_result\_t globus\_gass\_copy\_set\_user\_pointer ( globus\_gass\_copy\_handle\_t \* *handle*, void \* *user\_pointer* )

Set a pointer in the handle to point at user-allocated memory.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.28** globus\_result\_t globus\_gass\_copy\_get\_user\_pointer ( globus\_gass\_copy\_handle\_t \* *handle*, void \*\* *user\_data* )

Get the pointer in the handle that points to user-allocated memory.

References GLOBUS\_GASS\_COPY\_MODULE.

**5.1.2.29** globus\_result\_t globus\_gass\_copy\_cancel ( globus\_gass\_copy\_handle\_t \* *handle*, globus\_gass\_copy\_callback\_t *cancel\_callback*, void \* *cancel\_callback\_arg* )

Cancel the current transfer associated with this handle,.

store the cancel\_callback and cancel\_callback\_arg in the handle. Needed because the ftp callback will be the one given from the original globus\_ftp\_client\_third\_party\_transfer() call.

References GLOBUS\_GASS\_COPY\_MODULE, and globus\_i\_gass\_copy\_target\_cancel().

**5.1.2.30** globus\_result\_t globus\_i\_gass\_copy\_target\_cancel ( globus\_i\_gass\_copy\_cancel\_t \* *cancel\_info* )

Cancel the source or destination transfer in progress.

References GLOBUS\_GASS\_COPY\_MODULE, globus\_i\_gass\_copy\_state\_target\_s::mode, and globus\_i\_gass\_copy\_state\_target\_s::url.

## 5.2 globus\_gass\_copy.h File Reference

Header file for the gass copy library.

### Data Structures

- struct **globus\_gass\_copy\_glob\_stat\_t**  
*Glob expanded entry information.*

### Defines

- #define **GLOBUS\_GASS\_COPY\_MODULE** (&globus\_i\_gass\_copy\_module)

### Typedefs

- typedef void(\* **globus\_gass\_copy\_performance\_cb\_t**)(void \*user\_arg, globus\_gass\_copy\_handle\_t \*handle, globus\_off\_t total\_bytes, float instantaneous\_throughput, float avg\_throughput)
- typedef void(\* **globus\_gass\_copy\_glob\_entry\_cb\_t**)(const char \*url, const **globus\_gass\_copy\_glob\_stat\_t** \*info\_stat, void \*user\_arg)

## Enumerations

- enum **globus\_gass\_copy\_glob\_entry\_t**

## Functions

- globus\_result\_t **globus\_gass\_copy\_glob\_expand\_url** (globus\_gass\_copy\_handle\_t \*handle, const char \*url, globus\_gass\_copy\_attr\_t \*attr, **globus\_gass\_copy\_glob\_entry\_cb\_t** entry\_cb, void \*user\_arg)
- globus\_result\_t **globus\_gass\_copy\_mkdir** (globus\_gass\_copy\_handle\_t \*handle, char \*url, globus\_gass\_copy\_attr\_t \*attr)

### 5.2.1 Detailed Description

Header file for the gass copy library.

### 5.2.2 Define Documentation

#### 5.2.2.1 #define GLOBUS\_GASS\_COPY\_MODULE (&globus.i.gass\_copy.module)

Module descriptor.

Globus GASS Copy uses standard Globus module activation and deactivation. Before any Globus GASS Copy functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GASS_COPY_MODULE)
```

This function returns GLOBUS\_SUCCESS if Globus GASS Copy was successfully initialized, and you are therefore allowed to subsequently call Globus GASS Copy functions. Otherwise, an error code is returned, and Globus GASS Copy functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GASS Copy, the following function must be called:

```
globus_module_deactivate(GLOBUS_GASS_COPY_MODULE)
```

This function should be called once for each time Globus GASS Copy was activated.

### 5.2.3 Typedef Documentation

#### 5.2.3.1 typedef void(\* globus\_gass\_copy\_performance\_cb\_t)(void \*user\_arg, globus\_gass\_copy\_handle\_t \*handle, globus\_off\_t total\_bytes, float instantaneous\_throughput, float avg\_throughput)

Gass copy transfer performance callback.

This callback is registered with 'globus\_gass\_copy\_register\_performance\_cb'. It will be called during a transfer to supply performance information on current transfer. Its frequency will be at most one per second, but it is possible to receive no callbacks. This is possible in very short transfers and in ftp transfers in which the server does not provide performance information.

## Parameters

<i>handle</i>	the gass copy handle this transfer is occurring on
<i>user_arg</i>	a user pointer registered with 'globus_gass_copy_register_performance_cb'
<i>total_bytes</i>	the total number of bytes transfer so far
<i>instantaneous_throughput</i>	instantaneous rate of transfer (since last callback or start) (bytes / sec)
<i>avg_throughput</i>	the avg thoughput calculated since the start of the transfer (bytes / sec)

## Returns

- n/a

5.2.3.2 `typedef void(* globus_gass_copy_glob_entry_cb_t)(const char *url, const globus_gass_copy_glob_stat_t *info_stat, void *user_arg)`

Gass copy glob entry callback.

This callback is passed as a parameter to `globus_gass_copy_glob_expand_url()` (p. 20). It is called once for each entry that the original expands to.

## Parameters

<i>url</i>	The full url to the expanded entry. A directory entry will end in a forward slash '/'.
<i>stat</i>	A pointer to a <code>globus_gass_copy_glob_stat_t</code> (p. 2) containing information about the entry.
<i>user_arg</i>	The <code>user_arg</code> passed to <code>globus_gass_copy_glob_expand()</code>

## See also

`globus_gass_copy_glob_stat_t` (p. 2), `globus_gass_copy_glob_expand_url` (p. 20)

## 5.2.4 Enumeration Type Documentation

### 5.2.4.1 enum globus\_gass\_copy\_glob\_entry\_t

globbed entry types

## 5.2.5 Function Documentation

5.2.5.1 `globus_result_t globus_gass_copy_glob_expand_url ( globus_gass_copy_handle_t * handle, const char * url, globus_gass_copy_attr_t * attr, globus_gass_copy_glob_entry_cb_t entry_cb, void * user_arg )`

Expand globbed url.

This function expands wildcards in a globbed url, and calls `entry_cb()` on each one.

## Parameters

<i>handle</i>	A gass copy handle to use for the operation.
<i>url</i>	The URL to expand. The URL may be an ftp, gsiftp or file URL. Wildcard characters supported are '?' '*' '[' ]' in the filename portion of the url.
<i>attr</i>	Gass copy attributes for this operation.
<i>entry_cb</i>	Function to call with information about each entry
<i>user_arg</i>	An argument to pass to <code>entry_cb()</code>

## Returns

This function returns an error when any of these conditions are true:

- `handle` is `GLOBUS_NULL`
- `url` is `GLOBUS_NULL`
- `url` cannot be parsed
- `url` is not a ftp, gsiftp or file url

References `globus_gass_copy_glob_expand_url()`, `GLOBUS_GASS_COPY_MODULE`, `globus_gass_copy_glob_stat_t::mdtm`, `globus_gass_copy_glob_stat_t::mode`, `globus_gass_copy_glob_stat_t::size`, `globus_gass_copy_glob_stat_t::symlink_target`, `globus_gass_copy_glob_stat_t::type`, and `globus_gass_copy_glob_stat_t::unique_id`.

**5.2.5.2** `globus_result_t globus_gass_copy_mkdir ( globus_gass_copy_handle_t * handle, char * url, globus_gass_copy_attr_t * attr )`

Make directory.

This function creates a directory given a ftp or file url.

#### Parameters

<i>handle</i>	A gass copy handle to use for the mkdir operation.
<i>url</i>	The URL for the directory to create. The URL may be an ftp, gsiftp or file URL.
<i>attr</i>	Gass copy attributes for this operation.

#### Returns

This function returns an error when any of these conditions are true:

- `handle` is `GLOBUS_NULL`
- `url` is `GLOBUS_NULL`
- `url` cannot be parsed
- `url` is not a ftp, gsiftp or file url
- the directory could not be created

References `globus_gass_copy_get_url_mode()`, `globus_gass_copy_mkdir()`, and `GLOBUS_GASS_COPY_MODULE`.

## Index

- attr
  - globus\_i\_gass\_copy\_state\_target\_s, 4
- cancel
  - globus\_gass\_copy\_state\_s, 3
- dest
  - globus\_gass\_copy\_state\_s, 3
- free\_handle
  - globus\_i\_gass\_copy\_state\_target\_s, 5
- globus\_gass\_copy.c, 5
  - globus\_gass\_copy\_attr\_init, 9
  - globus\_gass\_copy\_attr\_set\_ftp, 10
  - globus\_gass\_copy\_attr\_set\_gass, 10
  - globus\_gass\_copy\_attr\_set\_io, 10
  - globus\_gass\_copy\_cache\_url\_state, 16
  - globus\_gass\_copy\_cancel, 17
  - globus\_gass\_copy\_flush\_url\_state, 16
  - globus\_gass\_copy\_get\_buffer\_length, 7
  - globus\_gass\_copy\_get\_no\_third\_party\_transfers, 8
  - globus\_gass\_copy\_get\_partial\_offsets, 9
  - globus\_gass\_copy\_get\_status, 12
  - globus\_gass\_copy\_get\_status\_string, 12
  - globus\_gass\_copy\_get\_url\_mode, 11
  - globus\_gass\_copy\_get\_user\_pointer, 17
  - globus\_gass\_copy\_handle\_destroy, 7
  - globus\_gass\_copy\_handle\_init, 6
  - globus\_gass\_copy\_handle\_to\_url, 14
  - globus\_gass\_copy\_register\_handle\_to\_url, 15
  - globus\_gass\_copy\_register\_performance\_cb, 11
  - globus\_gass\_copy\_register\_url\_to\_handle, 15
  - globus\_gass\_copy\_register\_url\_to\_url, 14
  - globus\_gass\_copy\_set\_allocate, 8
  - globus\_gass\_copy\_set\_buffer\_length, 7
  - globus\_gass\_copy\_set\_no\_third\_party\_transfers, 8
  - globus\_gass\_copy\_set\_partial\_offsets, 9
  - globus\_gass\_copy\_set\_stat\_on\_expand, 8
  - globus\_gass\_copy\_set\_user\_pointer, 17
  - globus\_gass\_copy\_url\_to\_handle, 13
  - globus\_gass\_copy\_url\_to\_url, 12
  - globus\_l\_gass\_copy\_target\_cancel, 17
- globus\_gass\_copy.h, 17
  - globus\_gass\_copy\_glob\_entry\_cb\_t, 19
  - globus\_gass\_copy\_glob\_entry\_t, 19
  - globus\_gass\_copy\_glob\_expand\_url, 19
  - globus\_gass\_copy\_mkdir, 19
  - GLOBUS\_GASS\_COPY\_MODULE, 18
  - globus\_gass\_copy\_performance\_cb\_t, 18
- globus\_gass\_copy\_attr\_init
  - globus\_gass\_copy.c, 9
- globus\_gass\_copy\_attr\_set\_ftp
  - globus\_gass\_copy.c, 10
- globus\_gass\_copy\_attr\_set\_gass
  - globus\_gass\_copy.c, 10
- globus\_gass\_copy\_attr\_set\_io
  - globus\_gass\_copy.c, 10
- globus\_gass\_copy\_cache\_url\_state
  - globus\_gass\_copy.c, 16
- globus\_gass\_copy\_cancel
  - globus\_gass\_copy.c, 17
- globus\_gass\_copy\_flush\_url\_state
  - globus\_gass\_copy.c, 16
- globus\_gass\_copy\_get\_buffer\_length
  - globus\_gass\_copy.c, 7
- globus\_gass\_copy\_get\_no\_third\_party\_transfers
  - globus\_gass\_copy.c, 8
- globus\_gass\_copy\_get\_partial\_offsets
  - globus\_gass\_copy.c, 9
- globus\_gass\_copy\_get\_status
  - globus\_gass\_copy.c, 12
- globus\_gass\_copy\_get\_status\_string
  - globus\_gass\_copy.c, 12
- globus\_gass\_copy\_get\_url\_mode
  - globus\_gass\_copy.c, 11
- globus\_gass\_copy\_get\_user\_pointer
  - globus\_gass\_copy.c, 17
- globus\_gass\_copy\_glob\_entry\_cb\_t
  - globus\_gass\_copy.h, 19
- globus\_gass\_copy\_glob\_entry\_t
  - globus\_gass\_copy.h, 19
- globus\_gass\_copy\_glob\_expand\_url
  - globus\_gass\_copy.h, 19
- globus\_gass\_copy\_glob\_stat\_t, 1
  - mdtm, 2
  - mode, 2
  - size, 2
  - symlink\_target, 2
  - type, 2
  - unique\_id, 2
- globus\_gass\_copy\_handle\_destroy
  - globus\_gass\_copy.c, 7
- globus\_gass\_copy\_handle\_init
  - globus\_gass\_copy.c, 6
- globus\_gass\_copy\_handle\_to\_url
  - globus\_gass\_copy.c, 14
- globus\_gass\_copy\_mkdir
  - globus\_gass\_copy.h, 19
- GLOBUS\_GASS\_COPY\_MODULE
  - globus\_gass\_copy.h, 18
- globus\_gass\_copy\_performance\_cb\_t
  - globus\_gass\_copy.h, 18
- globus\_gass\_copy\_register\_handle\_to\_url
  - globus\_gass\_copy.c, 15

globus_gass_copy_register_performance_cb	globus_i_gass_copy_state_target_s, 4
globus_gass_copy.c, 11	
globus_gass_copy_register_url_to_handle	n_complete
globus_gass_copy.c, 15	globus_i_gass_copy_state_target_s, 4
globus_gass_copy_register_url_to_url	n_pending
globus_gass_copy.c, 14	globus_i_gass_copy_state_target_s, 4
globus_gass_copy_set_allocate	n_simultaneous
globus_gass_copy.c, 8	globus_i_gass_copy_state_target_s, 4
globus_gass_copy_set_buffer_length	queue
globus_gass_copy.c, 7	globus_i_gass_copy_state_target_s, 4
globus_gass_copy_set_no_third_party_transfers	request
globus_gass_copy.c, 8	globus_i_gass_copy_state_target_s, 5
globus_gass_copy_set_partial_offsets	seekable
globus_gass_copy.c, 9	globus_i_gass_copy_state_target_s, 5
globus_gass_copy_set_stat_on_expand	size
globus_gass_copy.c, 8	globus_gass_copy_glob_stat_t, 2
globus_gass_copy_set_user_pointer	source
globus_gass_copy.c, 17	globus_gass_copy_state_s, 3
globus_gass_copy_state_s, 2	status
cancel, 3	globus_i_gass_copy_state_target_s, 5
dest, 3	symlink_target
monitor, 3	globus_gass_copy_glob_stat_t, 2
mutex, 3	
source, 3	type
globus_gass_copy_url_to_handle	globus_gass_copy_glob_stat_t, 2
globus_gass_copy.c, 13	
globus_gass_copy_url_to_url	unique_id
globus_gass_copy.c, 12	globus_gass_copy_glob_stat_t, 2
globus_i_gass_copy_buffer_t, 3	url
globus_i_gass_copy_cancel_s, 3	globus_i_gass_copy_state_target_s, 4
globus_i_gass_copy_monitor_t, 3	
globus_i_gass_copy_state_target_s, 4	
attr, 4	
free_handle, 5	
mode, 5	
mutex, 4	
n_complete, 4	
n_pending, 4	
n_simultaneous, 4	
queue, 4	
request, 5	
seekable, 5	
status, 5	
url, 4	
globus_l_gass_copy_target_cancel	
globus_gass_copy.c, 17	
mdtm	
globus_gass_copy_glob_stat_t, 2	
mode	
globus_gass_copy_glob_stat_t, 2	
globus_i_gass_copy_state_target_s, 5	
monitor	
globus_gass_copy_state_s, 3	
mutex	
globus_gass_copy_state_s, 3	