

globus common

10.2

Generated by Doxygen 1.5.9

Sun Aug 9 05:27:45 2009

Contents

1	Deprecated List	1
2	Module Index	1
2.1	Modules	1
3	Data Structure Index	1
3.1	Data Structures	1
4	File Index	2
4.1	File List	2
5	Module Documentation	2
5.1	Globus Callback	2
5.1.1	Detailed Description	2
5.1.2	Define Documentation	2
5.1.3	Typedef Documentation	3
5.1.4	Enumeration Type Documentation	3
5.2	Globus Callback API	4
5.2.1	Detailed Description	5
5.2.2	Define Documentation	5
5.2.3	Typedef Documentation	7
5.2.4	Function Documentation	7
5.3	Globus Callback Spaces	12
5.3.1	Detailed Description	13
5.3.2	Define Documentation	13
5.3.3	Enumeration Type Documentation	13
5.3.4	Function Documentation	13
5.4	Globus Callback Signal Handling	17
5.4.1	Detailed Description	17
5.4.2	Define Documentation	17
5.4.3	Function Documentation	17
5.5	Globus Erno Error API	19
5.5.1	Detailed Description	19
5.6	Error Construction	19
5.6.1	Detailed Description	20
5.6.2	Define Documentation	20
5.6.3	Function Documentation	20
5.7	Error Data Accessors and Modifiers	21

5.7.1	Detailed Description	21
5.7.2	Function Documentation	21
5.8	Error Handling Helpers	22
5.8.1	Detailed Description	22
5.8.2	Function Documentation	22
5.9	Globus Error API	23
5.9.1	Detailed Description	24
5.10	Globus Generic Error API	24
5.10.1	Detailed Description	24
5.11	Error Construction	25
5.11.1	Detailed Description	25
5.11.2	Define Documentation	25
5.11.3	Function Documentation	25
5.12	Error Data Accessors and Modifiers	27
5.12.1	Detailed Description	28
5.12.2	Function Documentation	28
5.13	Error Handling Helpers	31
5.13.1	Detailed Description	31
5.13.2	Function Documentation	32
5.14	Globus Thread API	33
5.14.1	Function Documentation	33
5.15	URL String Parser	34
5.15.1	Detailed Description	34
5.15.2	Enumeration Type Documentation	34
5.15.3	Function Documentation	35
6	Data Structure Documentation	38
6.1	globus_url_t Struct Reference	38
6.1.1	Detailed Description	39
6.1.2	Field Documentation	39
7	File Documentation	41
7.1	globus_callback.h File Reference	41
7.1.1	Detailed Description	43
7.2	globus_thread_common.h File Reference	43
7.2.1	Detailed Description	43

1 Deprecated List

Global [GLOBUS_POLL_MODULE](#)

2 Module Index

2.1 Modules

Here is a list of all modules:

Globus Callback	2
Globus Callback API	4
Globus Callback Spaces	12
Globus Callback Signal Handling	17
Globus Error API	23
Globus Errno Error API	19
Error Construction	19
Error Data Accessors and Modifiers	21
Error Handling Helpers	22
Globus Generic Error API	24
Error Construction	25
Error Data Accessors and Modifiers	27
Error Handling Helpers	31
Globus Thread API	33
URL String Parser	34

3 Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

globus_url_t (Parsed URLs)	38
---	---------------------------

4 File Index


4.1 File List

Here is a list of all documented files with brief descriptions:

5 Module Documentation

5.1 Globus Callback

Collaboration diagram for Globus Callback:



Modules

- [Globus Callback API](#)
- [Globus Callback Spaces](#)
- [Globus Callback Signal Handling](#)

Module Specific

- enum [globus_callback_error_type_t](#) {
[GLOBUS_CALLBACK_ERROR_INVALID_CALLBACK_HANDLE](#) = 1024,
[GLOBUS_CALLBACK_ERROR_INVALID_SPACE](#),
[GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC](#),
[GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT](#),
[GLOBUS_CALLBACK_ERROR_ALREADY_CANCELED](#),
[GLOBUS_CALLBACK_ERROR_NO_ACTIVE_CALLBACK](#) }
- typedef int [globus_callback_handle_t](#)
- typedef int [globus_callback_space_t](#)
- typedef struct [globus_l_callback_space_attr_s](#) * [globus_callback_space_attr_t](#)
- #define [GLOBUS_CALLBACK_MODULE](#)
- #define [GLOBUS_POLL_MODULE](#)

5.1.1 Detailed Description

5.1.2 Define Documentation

5.1.2.1 #define GLOBUS_CALLBACK_MODULE

Module descriptor for for globus_callback module.

Must be activated before any of the following api is called.

Note: You would not normally activate this module directly. Activating the GLOBUS_COMMON_MODULE will in turn activate this also.

5.1.2.2 `#define GLOBUS_POLL_MODULE`

Deprecated

Backward compatible name

5.1.3 Typedef Documentation

5.1.3.1 `typedef int globus_callback_handle_t`

Handle for a periodic callback.

This handle can be copied or compared, and represented as NULL with `GLOBUS_NULL_HANDLE`

5.1.3.2 `typedef int globus_callback_space_t`

Handle for a callback space.

This handle can be copied or compared and represented as NULL with `GLOBUS_NULL_HANDLE`

5.1.3.3 `typedef struct globus_l_callback_space_attr_s* globus_callback_space_attr_t`

Handle for a space attr.

This handle can be copied and represented as NULL with `GLOBUS_NULL`

5.1.4 Enumeration Type Documentation

5.1.4.1 `enum globus_callback_error_type_t`

Possible error types returned by the api in this module.

You can use the error API to check results against these types.

See also:

[Error Handling Helpers](#)

Enumerator:

`GLOBUS_CALLBACK_ERROR_INVALID_CALLBACK_HANDLE` The callback handle is not valid or it has already been destroyed.

`GLOBUS_CALLBACK_ERROR_INVALID_SPACE` The space handle is not valid or it has already been destroyed.

`GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC` Could not allocate memory for an internal structure.

GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT One of the arguments is NULL or out of range.

GLOBUS_CALLBACK_ERROR_ALREADY_CANCELED Attempt to unregister callback again.

GLOBUS_CALLBACK_ERROR_NO_ACTIVE_CALLBACK Attempt to retrieve info about a callback not in callers's stack.

5.2 Globus Callback API

Collaboration diagram for Globus Callback API:



Callback Prototypes

- typedef void(* [globus_callback_func_t](#))(void *user_arg)

Oneshot Callbacks

- globus_result_t [globus_callback_space_register_oneshot](#) ([globus_callback_handle_t](#) *callback_handle, const globus_retime_t *delay_time, [globus_callback_func_t](#) callback_func, void *callback_user_arg, [globus_callback_space_t](#) space)

Periodic Callbacks

- globus_result_t [globus_callback_space_register_periodic](#) ([globus_callback_handle_t](#) *callback_handle, const globus_retime_t *delay_time, const globus_retime_t *period, [globus_callback_func_t](#) callback_func, void *callback_user_arg, [globus_callback_space_t](#) space)
- globus_result_t [globus_callback_unregister](#) ([globus_callback_handle_t](#) callback_handle, [globus_callback_func_t](#) unregister_callback, void *unreg_arg, globus_bool_t *active)
- globus_result_t [globus_callback_adjust_oneshot](#) ([globus_callback_handle_t](#) callback_handle, const globus_retime_t *new_delay)
- globus_result_t [globus_callback_adjust_period](#) ([globus_callback_handle_t](#) callback_handle, const globus_retime_t *new_period)

Callback Polling

- void [globus_callback_space_poll](#) (const globus_abstime_t *timestop, [globus_callback_space_t](#) space)
- void [globus_callback_signal_poll](#) ()

Miscellaneous

- globus_bool_t [globus_callback_get_timeout](#) (globus_retime_t *time_left)
- globus_bool_t [globus_callback_has_time_expired](#) ()
- globus_bool_t [globus_callback_was_restarted](#) ()

Convenience Macros

- `#define globus_callback_poll(a)`
- `#define globus_poll_blocking()`
- `#define globus_poll_nonblocking()`
- `#define globus_poll()`
- `#define globus_signal_poll()`
- `#define globus_callback_register_onehot(callback_handle,delay_time,callback_func,callback_user_arg)`
- `#define globus_callback_register_periodic(callback_handle,delay_time,period,callback_func,callback_user_arg)`
- `#define globus_callback_register_signal_handler(signum,persist,callback_func,callback_user_arg)`

5.2.1 Detailed Description

5.2.2 Define Documentation

5.2.2.1 `#define globus_callback_poll(a)`

Specifies the global space for `globus_callback_space_poll()`.

argument is the timeout

See also:

`globus_callback_space_poll()`

5.2.2.2 `#define globus_poll_blocking()`

Specifies that `globus_callback_space_poll()` should poll on the global space with an infinite timeout.

See also:

`globus_callback_space_poll()`

5.2.2.3 `#define globus_poll_nonblocking()`

Specifies that `globus_callback_space_poll()` should poll on the global space with an immediate timeout.

See also:

`globus_callback_space_poll()`

5.2.2.4 `#define globus_poll()`

Specifies that `globus_callback_space_poll()` should poll on the global space with an immediate timeout.

See also:

`globus_callback_space_poll()`

5.2.2.5 `#define globus_signal_poll()`

Counterpart to [globus_poll\(\)](#).

See also:

[globus_callback_signal_poll\(\)](#)

5.2.2.6 `#define globus_callback_register_oneshot(callback_handle, delay_time, callback_func, callback_user_arg)`

Specifies the global space for [globus_callback_space_register_oneshot\(\)](#) all other arguments are the same as specified there.

See also:

[globus_callback_space_register_oneshot\(\)](#)

5.2.2.7 `#define globus_callback_register_periodic(callback_handle, delay_time, period, callback_func, callback_user_arg)`

Specifies the global space for [globus_callback_space_register_periodic\(\)](#) all other arguments are the same as specified there.

See also:

[globus_callback_space_register_periodic\(\)](#)

5.2.2.8 `#define globus_callback_register_signal_handler(signum, persist, callback_func, callback_user_arg)`

Specifies the global space for [globus_callback_space_register_signal_handler\(\)](#) all other arguments are the same as specified there.

See also:

[globus_callback_space_register_signal_handler\(\)](#)

5.2.3 Typedef Documentation

5.2.3.1 `typedef void(* globus_callback_func_t)(void *user_arg)`

Globus callback prototype.

This is the signature of the function registered with the `globus_callback_register_*` calls.

If this is a periodic callback, it is guaranteed that the call canNOT be reentered unless `globus_thread_blocking_space_will_block()` is called (explicitly, or implicitly via `globus_cond_wait()`). Also, if [globus_callback_unregister\(\)](#) is called to cancel this periodic from within this callback, it is guaranteed that the callback will NOT be requested again

If the function will block at all, the user should call [globus_callback_get_timeout\(\)](#) to see how long this function can safely block or call `globus_thread_blocking_space_will_block()`

Parameters:

user_arg The user argument registered with this callback

Returns:

- void

See also:

[globus_callback_space_register_oneshot\(\)](#)
[globus_callback_space_register_periodic\(\)](#)
[globus_thread_blocking_space_will_block\(\)](#)
[globus_callback_get_timeout\(\)](#)

5.2.4 Function Documentation

5.2.4.1 `globus_result_t globus_callback_space_register_oneshot (globus_callback_handle_t * callback_handle, const globus_reftime_t * delay_time, globus_callback_func_t callback_func, void * callback_user_arg, globus_callback_space_t space)`

Register a oneshot some delay from now.

This function registers the `callback_func` to start some `delay_time` from now.

Parameters:

callback_handle Storage for a handle. This may be NULL. If it is NOT NULL, you must unregister the callback to reclaim resources.

delay_time The relative time from now to fire this callback. If NULL, will fire as soon as possible

callback_func the user func to call

callback_user_arg user arg that will be passed to callback

space The space with which to register this callback

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT
- GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC
- GLOBUS_SUCCESS

See also:

[globus_callback_func_t](#)
[Globus Callback Spaces](#)

5.2.4.2 **globus_result_t globus_callback_space_register_periodic (globus_callback_handle_t * callback_handle, const globus_retime_t * delay_time, const globus_retime_t * period, globus_callback_func_t callback_func, void * callback_user_arg, globus_callback_space_t space)**

Register a periodic callback.

This function registers a periodic callback_func to start some delay_time and run every period from then.

Parameters:

callback_handle Storage for a handle. This may be NULL. If it is NOT NULL, you must cancel the periodic to reclaim resources.

delay_time The relative time from now to fire this callback. If NULL, will fire the first callback as soon as possible

period The relative period of this callback

callback_func the user func to call

callback_user_arg user arg that will be passed to callback

space The space with which to register this callback

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT
- GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC
- GLOBUS_SUCCESS

See also:

[globus_callback_unregister\(\)](#)
[globus_callback_func_t](#)
[Globus Callback Spaces](#)

5.2.4.3 **globus_result_t globus_callback_unregister (globus_callback_handle_t callback_handle, globus_callback_func_t unregister_callback, void * unreg_arg, globus_bool_t * active)**

Unregister a callback.

This function will cancel a callback and free the resources associated with the callback handle. If the callback was able to be canceled immediately (or if it has already run), GLOBUS_SUCCESS is returned and it is guaranteed that there are no running instances of the callback.

If the callback is currently running (or unstoppably about to be run), then the callback is prevented from being requeued, but, the 'official' cancel is deferred until the last running instance of the callback returns. If you need to know when the callback is guaranteed to have been canceled, pass an unregister callback.

If you would like to know if you unregistered a callback before it ran, pass storage for a boolean 'active'. This will be GLOBUS_TRUE if callback was running. GLOBUS_FALSE otherwise.

Parameters:

callback_handle the handle received from a globus_callback_space_register_*() call

unregister_callback the function to call when the callback has been canceled and there are no running instances of it. This will be delivered to the same space used in the register call.

unreg_arg user arg that will be passed to the unregister callback

active storage for an indication of whether the callback was running when this call was made

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_CALLBACK_HANDLE
- GLOBUS_CALLBACK_ERROR_ALREADY_CANCELED
- GLOBUS_SUCCESS

See also:

[globus_callback_space_register_periodic\(\)](#)
[globus_callback_func_t](#)

**5.2.4.4 globus_result_t globus_callback_adjust_oneshot (globus_callback_handle_t *callback_handle*,
const globus_retime_t * *new_delay*)**

Adjust the delay of a oneshot callback.

This function allows a user to adjust the delay of a previously registered callback. It is safe to call this within or outside of the callback that is being modified.

Note if the oneshot has already been fired, this function will still return GLOBUS_SUCCESS, but won't affect anything.

Parameters:

callback_handle the handle received from a [globus_callback_space_register_oneshot\(\)](#) call

new_delay The new delay from now. If NULL, then callback will be fired as soon as possible.

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_CALLBACK_HANDLE
- GLOBUS_CALLBACK_ERROR_ALREADY_CANCELED
- GLOBUS_SUCCESS

See also:

[globus_callback_space_register_periodic\(\)](#)

**5.2.4.5 globus_result_t globus_callback_adjust_period (globus_callback_handle_t *callback_handle*,
const globus_retime_t * *new_period*)**

Adjust the period of a periodic callback.

This function allows a user to adjust the period of a previously registered callback. It is safe to call this within or outside of the callback that is being modified.

This func also allows a user to effectively 'suspend' a periodic callback until another time by passing a period of NULL. The callback can later be resumed by passing in a new period.

Note that the callback will not be fired sooner than 'new_period' from now. A 'suspended' callback must still be unregistered to free its resources.

Parameters:

callback_handle the handle received from a [globus_callback_space_register_periodic\(\)](#) call

new_period The new period. If NULL or `globus_i_retime_infinity`, then callback will be 'suspended' as soon as the last running instance of it returns.

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_CALLBACK_HANDLE
- GLOBUS_CALLBACK_ERROR_ALREADY_CANCELED
- GLOBUS_SUCCESS

See also:

[globus_callback_space_register_periodic\(\)](#)

5.2.4.6 void globus_callback_space_poll (const globus_abstime_t * *timestop*, globus_callback_space_t *space*)

Poll for ready callbacks.

This function is used to poll for registered callbacks.

For non-threaded builds, callbacks are not/can not be delivered unless this is called. Any call to this can cause callbacks registered with the 'global' space to be fired. Whereas callbacks registered with a user's space will only be delivered when this is called with that space.

For threaded builds, this only needs to be called to poll user spaces with `behavior == GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE`. The 'global' space and other user spaces are constantly polled in a separate thread. (If it is called in a threaded build for these spaces, it will just yield its thread)

In general, you never need to call this function directly. It is called (when necessary) by `globus_cond_wait()`. The only case in which a user may wish to call this explicitly is if the application has no aspirations of ever being built threaded.

This function (when not yielding) will block up to *timestop* or until [globus_callback_signal_poll\(\)](#) is called by one of the fired callbacks. It will always try and kick out ready callbacks, regardless of the *timestop*.

Parameters:

timestop The time to block until. If this is NULL or less than the current time, an attempt to fire only ready callbacks is made (no blocking).

space The callback space to poll. Note: regardless of what space is passed here, the 'global' space is also always polled.

Returns:

- void

See also:

[Globus Callback Spaces](#)
[globus_condattr_setspace\(\)](#)

5.2.4.7 void globus_callback_signal_poll ()

Signal the poll.

This function signals [globus_callback_space_poll\(\)](#) that something has changed and it should return to its caller as soon as possible.

In general, you never need to call this function directly. It is called (when necessary) by `globus_cond_signal()` or `globus_cond_broadcast`. The only case in which a user may wish to call this explicitly is if the application has no aspirations of ever being built threaded.

Returns:

- void

See also:

[globus_callback_space_poll\(\)](#)

5.2.4.8 globus_bool_t globus_callback_get_timeout (globus_retime_t * *time_left*)

Get the amount of time left in a callback.

This function retrieves the remaining time a callback is allowed to run. If a callback has already timed out, `time_left` will be set to zero and `GLOBUS_TRUE` returned. This function is intended to be called within a callback's stack, but is harmless to call anywhere (will return `GLOBUS_FALSE` and an infinite `time_left`)

Parameters:

time_left storage for the remaining time.

Returns:

- `GLOBUS_FALSE` if time remaining
- `GLOBUS_TRUE` if already timed out

5.2.4.9 globus_bool_t globus_callback_has_time_expired ()

See if there is remaining time in a callback.

This function returns `GLOBUS_TRUE` if the running time of a callback has already expired. This function is intended to be called within a callback's stack, but is harmless to call anywhere (will return `GLOBUS_FALSE`)

Returns:

- `GLOBUS_FALSE` if time remaining
- `GLOBUS_TRUE` if already timed out

5.2.4.10 globus_bool_t globus_callback_was_restarted ()

See if a callback has been restarted.

If the callback is a oneshot, this merely means the callback called globus_thread_blocking_space_will_block (or globus_cond_wait()) at some point.

For a periodic, it signifies the same and also that the periodic has been requeued. This means that the callback function may be reentered if the period is short enough (on a threaded build)

Returns:

- GLOBUS_FALSE if not restarted
- GLOBUS_TRUE if restarted

5.3 Globus Callback Spaces

Collaboration diagram for Globus Callback Spaces:



Defines

- #define GLOBUS_CALLBACK_GLOBAL_SPACE

Enumerations

- enum globus_callback_space_behavior_t {
 GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE,
 GLOBUS_CALLBACK_SPACE_BEHAVIOR_SERIALIZED,
 GLOBUS_CALLBACK_SPACE_BEHAVIOR_THREADED }

Functions

- globus_result_t globus_callback_space_init (globus_callback_space_t *space, globus_callback_space_attr_t attr)
- globus_result_t globus_callback_space_reference (globus_callback_space_t space)
- globus_result_t globus_callback_space_destroy (globus_callback_space_t space)
- globus_result_t globus_callback_space_attr_init (globus_callback_space_attr_t *attr)
- globus_result_t globus_callback_space_attr_destroy (globus_callback_space_attr_t attr)
- globus_result_t globus_callback_space_attr_set_behavior (globus_callback_space_attr_t attr, globus_callback_space_behavior_t behavior)
- globus_result_t globus_callback_space_attr_get_behavior (globus_callback_space_attr_t attr, globus_callback_space_behavior_t *behavior)
- globus_result_t globus_callback_space_get (globus_callback_space_t *space)
- int globus_callback_space_get_depth (globus_callback_space_t space)
- globus_bool_t globus_callback_space_is_single (globus_callback_space_t space)

5.3.1 Detailed Description

5.3.2 Define Documentation

5.3.2.1 #define GLOBUS_CALLBACK_GLOBAL_SPACE

The 'global' space handle.

This is the default space handle implied if no spaces are explicitly created.

5.3.3 Enumeration Type Documentation

5.3.3.1 enum globus_callback_space_behavior_t

Callback space behaviors describe how a space behaves.

In a non-threaded build all spaces exhibit a behavior == `_BEHAVIOR_SINGLE`. Setting a specific behavior in this case is ignored.

In a threaded build, `_BEHAVIOR_SINGLE` retains all the rules and behaviors of a non-threaded build while `_BEHAVIOR_THREADED` makes the space act as the global space.

Setting a space's behavior to `_BEHAVIOR_SINGLE` guarantees that the poll protection will always be there and all callbacks are serialized and only kicked out when polled for. In a threaded build, it is still necessary to poll for callbacks in a `_BEHAVIOR_SINGLE` space. (`globus_cond_wait()` will take care of this for you also)

Setting a space's behavior to `_BEHAVIOR_SERIALIZED` guarantees that the poll protection will always be there and all callbacks are serialized. In a threaded build, it is NOT necessary to poll for callbacks in a `_BEHAVIOR_SERIALIZED` space. Callbacks in this space will be delivered as soon as possible, but only one outstanding (and unblocked) callback will be allowed at any time.

Setting a space's behavior to `_BEHAVIOR_THREADED` allows the user to have the poll protection provided by spaces when built non-threaded, yet, be fully threaded when built threaded (where poll protection is not needed)

Enumerator:

GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE The default behavior.

Indicates that you always want poll protection and single threaded behavior (callbacks need to be explicitly polled for)

GLOBUS_CALLBACK_SPACE_BEHAVIOR_SERIALIZED Indicates that you want poll protection and all callbacks to be serialized (but they do not need to be polled for in a threaded build).

GLOBUS_CALLBACK_SPACE_BEHAVIOR_THREADED Indicates that you only want poll protection.

5.3.4 Function Documentation

5.3.4.1 globus_result_t globus_callback_space_init (globus_callback_space_t * space, globus_callback_space_attr_t attr)

Initialize a user space.

This creates a user space.

Parameters:

space storage for the initialized space handle. This must be destroyed with [globus_callback_space_destroy\(\)](#)
attr a space attr describing desired behaviors. If GLOBUS_NULL, the default behavior of GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE is assumed. This attr is copied into the space, so it is acceptable to destroy the attr as soon as it is no longer needed

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT on NULL space
- GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC
- GLOBUS_SUCCESS

See also:

[globus_condattr_setspace\(\)](#)

5.3.4.2 globus_result_t globus_callback_space_reference (globus_callback_space_t space)

Take a reference to a space.

A library which has been 'given' a space to provide callbacks on would use this to take a reference on the user's space. This prevents mayhem should a user destroy a space before the library is done with it. This reference should be destroyed with [globus_callback_space_destroy\(\)](#) (think dup())

Parameters:

space space to reference

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_SPACE
- GLOBUS_SUCCESS

5.3.4.3 globus_result_t globus_callback_space_destroy (globus_callback_space_t space)

Destroy a reference to a user space.

This will destroy a reference to a previously initialized space. Space will not actually be destroyed until all callbacks registered with this space have been run and unregistered (if the user has a handle to that callback) AND all references (from [globus_callback_space_reference\(\)](#)) have been destroyed.

Parameters:

space space to destroy, previously initialized by [globus_callback_space_init\(\)](#) or referenced with [globus_callback_space_reference\(\)](#)

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_SPACE
- GLOBUS_SUCCESS

See also:

[globus_callback_space_init\(\)](#)
[globus_callback_space_reference\(\)](#)

5.3.4.4 `globus_result_t globus_callback_space_attr_init (globus_callback_space_attr_t * attr)`

Initialize a space attr.

Currently, the only attr to set is the behavior. The default behavior associated with this attr is `GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE`

Parameters:

attr storage for the initialized attr. Must be destroyed with [globus_callback_space_attr_destroy\(\)](#)

Returns:

- `GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT` on NULL attr
- `GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC`
- `GLOBUS_SUCCESS`

5.3.4.5 `globus_result_t globus_callback_space_attr_destroy (globus_callback_space_attr_t attr)`

Destroy a space attr.

Parameters:

attr attr to destroy, previously initialized with [globus_callback_space_attr_init\(\)](#)

Returns:

- `GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT` on NULL attr
- `GLOBUS_SUCCESS`

See also:

[globus_callback_space_attr_init\(\)](#)

5.3.4.6 `globus_result_t globus_callback_space_attr_set_behavior (globus_callback_space_attr_t attr, globus_callback_space_behavior_t behavior)`

Set the behavior of a space.

Parameters:

attr attr to associate behavior with
behavior desired behavior

Returns:

- `GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT`
- `GLOBUS_SUCCESS`

See also:

[globus_callback_space_behavior_t](#)

5.3.4.7 **globus_result_t globus_callback_space_attr_get_behavior (globus_callback_space_attr_t *attr*, globus_callback_space_behavior_t * *behavior*)**

Get the behavior associated with an attr.

Note: for a non-threaded build, this will always pass back a behavior == GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE.

Parameters:

attr attr on which to query behavior

behavior storage for the behavior

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT
- GLOBUS_SUCCESS

5.3.4.8 **globus_result_t globus_callback_space_get (globus_callback_space_t * *space*)**

Retrieve the space of a currently running callback.

Parameters:

space storage for the handle to the space currently running

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT on NULL space
- GLOBUS_CALLBACK_ERROR_NO_ACTIVE_CALLBACK
- GLOBUS_SUCCESS

5.3.4.9 **int globus_callback_space_get_depth (globus_callback_space_t *space*)**

Retrieve the current nesting level of a space.

Parameters:

space The space to query.

Returns:

- the current nesting level
- -1 on invalid space

5.3.4.10 globus_bool_t globus_callback_space_is_single (globus_callback_space_t *space*)

See if the specified space is a single threaded behavior space.

Parameters:

space the space to query

Returns:

- GLOBUS_TRUE if space's behavior is _BEHAVIOR_SINGLE
- GLOBUS_FALSE otherwise

5.4 Globus Callback Signal Handling

Collaboration diagram for Globus Callback Signal Handling:



Defines

- #define [GLOBUS_SIGNAL_INTERRUPT](#)

Functions

- globus_result_t [globus_callback_space_register_signal_handler](#) (int *signum*, globus_bool_t *persist*, [globus_callback_func_t](#) *callback_func*, void **callback_user_arg*, [globus_callback_space_t](#) *space*)
- globus_result_t [globus_callback_unregister_signal_handler](#) (int *signum*, [globus_callback_func_t](#) *unregister_callback*, void **unreg_arg*)
- void [globus_callback_add_wakeup_handler](#) (void(**wakeup*)(void *), void **user_arg*)

5.4.1 Detailed Description

5.4.2 Define Documentation

5.4.2.1 #define GLOBUS_SIGNAL_INTERRUPT

Use this to trap interrupts (SIGINT on unix).

In the future, this will also map to handle ctrl-C on win32.

5.4.3 Function Documentation

5.4.3.1 globus_result_t globus_callback_space_register_signal_handler (int *signum*, globus_bool_t *persist*, globus_callback_func_t *callback_func*, void * *callback_user_arg*, globus_callback_space_t *space*)

Fire a callback when the specified signal is received.

Note that there is a tiny delay between the time this call returns and the signal is actually handled by this library. It is likely that, if the signal was received the instant the call returned, it will be lost (this is normally not an issue, since you would call this in your startup code anyway)

Parameters:

signum The signal to receive. The following signals are not allowed: SIGKILL, SIGSEGV, SIGABRT, SIGBUS, SIGFPE, SIGILL, SIGIOT, SIGPIPE, SIGEMT, SIGSYS, SIGTRAP, SIGSTOP, SIGCONT, and SIGWAITING

persist If GLOBUS_TRUE, keep this callback registered for multiple signals. If GLOBUS_FALSE, the signal handler will automatically be unregistered once the signal has been received.

callback_func the user func to call when a signal is received

callback_user_arg user arg that will be passed to callback

space the space to deliver callbacks to.

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_SPACE
- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT
- GLOBUS_SUCCESS otherwise

5.4.3.2 globus_result_t globus_callback_unregister_signal_handler (int *signum*, globus_callback_func_t *unregister_callback*, void * *unreg_arg*)

Unregister a signal handling callback.

Parameters:

signum The signal to unregister.

unregister_callback the function to call when the callback has been canceled and there are no running instances of it (may be NULL). This will be delivered to the same space used in the register call.

unreg_arg user arg that will be passed to callback

Returns:

- GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT if this signal was registered with persist == false, then there is a race between a signal actually being caught and therefor automatically unregistered and the attempt to manually unregister it. If that race occurs, you will receive this error just as you would for any signal not registered.
- GLOBUS_SUCCESS otherwise

5.4.3.3 void globus_callback_add_wakeup_handler (void(*)(void *) *wakeup*, void * *user_arg*)

Register a wakeup handler with callback library.

This is really only needed in non-threaded builds, but for cross builds should be used everywhere that a callback may sleep for an extended period of time.

An example use is for an io poller that sleeps indefinitely on select(). If the callback library receives a signal that it needs to deliver asap, it will call the wakeup handler(s). These wakeup handlers must run as though they were called from a signal handler (dont use any thread utilities). The io poll example will likely write a single byte to a pipe that select() is monitoring.

This handler will not be unregistered until the callback library is deactivated (via common).


Parameters:

wakeup function to call when callback library needs you to return asap from any blocked callbacks.

user_arg user data that will be passed along in the wakeup handler

5.5 Globus Errno Error API

Collaboration diagram for Globus Errno Error API:



Modules

- [Error Construction](#)
- [Error Data Accessors and Modifiers](#)
- [Error Handling Helpers](#)

5.5.1 Detailed Description

These globus_error functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g. memory management, chaining) of the current error handling framework. The functions in this API are auxiliary to the function in the Globus Generic Error API in the sense that they provide a wrapper for representing system errors in terms of a globus_error_t.

Any program that uses Globus Errno Error functions must include "globus_common.h".

5.6 Error Construction

Create and initialize a Globus Errno Error object.

Collaboration diagram for Error Construction:



Defines

- `#define GLOBUS_ERROR_TYPE_ERRNO`

Construct Error

- `globus_object_t * globus_error_construct_errno_error (globus_module_descriptor_t *base_source, globus_object_t *base_cause, const int system_errno)`

Initialize Error

- `globus_object_t * globus_error_initialize_errno_error (globus_object_t *error, globus_module_descriptor_t *base_source, globus_object_t *base_cause, const int system_errno)`

5.6.1 Detailed Description

Create and initialize a Globus Errno Error object.

This section defines operations to create and initialize Globus Errno Error objects.

5.6.2 Define Documentation

5.6.2.1 #define GLOBUS_ERROR_TYPE_ERRNO

Error type definition.

5.6.3 Function Documentation

5.6.3.1 `globus_object_t* globus_error_construct_errno_error (globus_module_descriptor_t *base_source, globus_object_t *base_cause, const int system_errno)`

Allocate and initialize an error of type GLOBUS_ERROR_TYPE_ERRNO.

Parameters:

base_source Pointer to the originating module.

base_cause The error object causing the error. If this is the original error, this parameter may be NULL.

system_errno The system errno.

Returns:

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

References `globus_error_initialize_errno_error()`, and `GLOBUS_ERROR_TYPE_ERRNO`.

5.6.3.2 `globus_object_t* globus_error_initialize_errno_error (globus_object_t *error, globus_module_descriptor_t *base_source, globus_object_t *base_cause, const int system_errno)`

Initialize a previously allocated error of type GLOBUS_ERROR_TYPE_ERRNO.

Parameters:

- error* The previously allocated error object.
- base_source* Pointer to the originating module.
- base_cause* The error object causing the error. If this is the original error this parameter may be NULL.
- system_errno* The system errno.

Returns:

The resulting error object. You may have to call `globus_error_put()` on this object before passing it on.

5.7 Error Data Accessors and Modifiers

Get and set data in a Globus Errno Error object.

Collaboration diagram for Error Data Accessors and Modifiers:

**Get Errno**

- int `globus_error_errno_get_errno` (globus_object_t *error)

Set Errno

- void `globus_error_errno_set_errno` (globus_object_t *error, const int system_errno)

5.7.1 Detailed Description

Get and set data in a Globus Errno Error object.

This section defines operations for accessing and modifying data in a Globus Errno Error object.

5.7.2 Function Documentation

5.7.2.1 int globus_error_errno_get_errno (globus_object_t * error)

Retrieve the system errno from a errno error object.

Parameters:

- error* The error from which to retrieve the errno

Returns:

The errno stored in the object

5.7.2.2 void globus_error_errno_set_errno (globus_object_t * error, const int system_errno)

Set the errno in a errno error object.

Parameters:

- error* The error object for which to set the errno
- system_errno* The system errno

Returns:

void

5.8 Error Handling Helpers

Helper functions for dealing with Globus Errno Error objects.

Collaboration diagram for Error Handling Helpers:



Error Match

- globus_bool_t [globus_error_errno_match](#) (globus_object_t *error, globus_module_descriptor_t *module, int system_errno)

Wrap Errno Error

- globus_object_t * [globus_error_wrap_errno_error](#) (globus_module_descriptor_t *base_source, int system_errno, int type, const char *source_file, const char *source_func, int source_line, const char *short_desc_format,...)

5.8.1 Detailed Description

Helper functions for dealing with Globus Errno Error objects.

This section defines utility functions for dealing with Globus Errno Error objects.

5.8.2 Function Documentation

5.8.2.1 globus_bool_t globus_error_errno_match (globus_object_t * error, globus_module_descriptor_t * module, int system_errno)

Check whether the error originated from a specific module and matches a specific errno.

This function checks whether the error or any of its causative errors originated from a specific module and contains a specific errno. If the module descriptor is left unspecified this function will check for any error of the specified errno and vice versa.

Parameters:

error The error object for which to perform the check
module The module descriptor to check for
system_errno The errno to check for

Returns:

GLOBUS_TRUE - the error matched the module and errno GLOBUS_FALSE - the error failed to match the module and errno

References globus_error_errno_get_errno(), globus_error_get_cause(), globus_error_get_source(), and GLOBUS_ERROR_TYPE_ERRNO.

5.8.2.2 globus_object_t* globus_error_wrap_errno_error (globus_module_descriptor_t * base_source, int system_errno, int type, const char * source_file, const char * source_func, int source_line, const char * short_desc_format, ...)

Allocate and initialize an error of type GLOBUS_ERROR_TYPE_GLOBUS which contains a causal error of type GLOBUS_ERROR_TYPE_ERRNO.

Parameters:

base_source Pointer to the originating module.
system_errno The errno to use when generating the causal error.
type The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.
source_file Name of file. Use __FILE__
source_func Name of function. Use _globus_func_name and declare your func with GlobusFuncName(<name>)
source_line Line number. Use __LINE__
short_desc_format Short format string giving a succinct description of the error. To be passed on to the user.
... Arguments for the format string.

Returns:


The resulting error object. It is the user's responsibility to eventually free this object using globus_object_free(). A globus_result_t may be obtained by calling globus_error_put() on this object.

References globus_error_construct_errno_error(), and globus_error_v_construct_error().

5.9 Globus Error API

Intended use:.

Collaboration diagram for Globus Error API:



Modules

- [Globus Errno Error API](#)
- [Globus Generic Error API](#)

5.9.1 Detailed Description

Intended use:.

If a function needs to return an error it should do the following:


- External errors, such as error returns from system calls and GSSAPI errors, should be wrapped using the appropriate error type.
- The wrapped external error should then be passed as the cause of a globus error.
- External error types are expected to provide a utility function to combine the above two steps.
- The globus error should then be returned from the function.

Notes on how to generate globus errors:

- Module specific error types should be greater or equal to 1024 (to leave some space for global error types).
- You may wish to generate a mapping from error types to format strings for use in short descriptions.
- You may also wish to generate a common prefix for all of the above format strings. The suggested prefix is "Function: s Line: s".

5.10 Globus Generic Error API

Collaboration diagram for Globus Generic Error API:



Modules

- [Error Construction](#)
- [Error Data Accessors and Modifiers](#)
- [Error Handling Helpers](#)

5.10.1 Detailed Description

These globus_error functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g. memory management, chaining) of the current error handling framework. It does this by defining a generic error type for globus which in turn contains a integer in it's instance data which is used for carrying the actual error type information.

Any program that uses Globus Generic Error functions must include "globus_common.h".

5.11 Error Construction

Create and initialize a Globus Generic Error object.

Collaboration diagram for Error Construction:



Defines

- `#define` [GLOBUS_ERROR_TYPE_GLOBUS](#)

Construct Error

- `globus_object_t *` [globus_error_construct_error](#) (`globus_module_descriptor_t *base_source`, `globus_object_t *base_cause`, `int type`, `const char *source_file`, `const char *source_func`, `int source_line`, `const char *short_desc_format`,...)
- `globus_object_t *` [globus_error_v_construct_error](#) (`globus_module_descriptor_t *base_source`, `globus_object_t *base_cause`, `const int type`, `const char *source_file`, `const char *source_func`, `int source_line`, `const char *short_desc_format`, `va_list ap`)

Initialize Error

- `globus_object_t *` [globus_error_initialize_error](#) (`globus_object_t *error`, `globus_module_descriptor_t *base_source`, `globus_object_t *base_cause`, `int type`, `const char *source_file`, `const char *source_func`, `int source_line`, `const char *short_desc_format`, `va_list ap`)

5.11.1 Detailed Description

Create and initialize a Globus Generic Error object.

This section defines operations to create and initialize Globus Generic Error objects.

5.11.2 Define Documentation

5.11.2.1 `#define` [GLOBUS_ERROR_TYPE_GLOBUS](#)

Error type definition.

5.11.3 Function Documentation

5.11.3.1 `globus_object_t*` [globus_error_construct_error](#) (`globus_module_descriptor_t *base_source`, `globus_object_t *base_cause`, `int type`, `const char *source_file`, `const char *source_func`, `int source_line`, `const char *short_desc_format`, ...)

Allocate and initialize an error of type `GLOBUS_ERROR_TYPE_GLOBUS`.

Parameters:

base_source Pointer to the originating module.

base_cause The error object causing the error. If this is the original error this parameter may be NULL.

type The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.

source_file Name of file. Use `__FILE__`

source_func Name of function. Use `_globus_func_name` and declare your func with `GlobusFuncName(<name>)`

source_line Line number. Use `__LINE__`

short_desc_format Short format string giving a succinct description of the error. To be passed on to the user.

... Arguments for the format string.

Returns:

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

References `globus_error_initialize_error()`, and `GLOBUS_ERROR_TYPE_GLOBUS`.

5.11.3.2 `globus_object_t* globus_error_v_construct_error (globus_module_descriptor_t * base_source, globus_object_t * base_cause, const int type, const char * source_file, const char * source_func, int source_line, const char * short_desc_format, va_list ap)`

Allocate and initialize an error of type `GLOBUS_ERROR_TYPE_GLOBUS`.

Parameters:

base_source Pointer to the originating module.

base_cause The error object causing the error. If this is the original error this parameter may be NULL.

type The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.

source_file Name of file. Use `__FILE__`

source_func Name of function. Use `_globus_func_name` and declare your func with `GlobusFuncName(<name>)`

source_line Line number. Use `__LINE__`

short_desc_format Short format string giving a succinct description of the error. To be passed on to the user.

ap Arguments for the format string.

Returns:

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

References `globus_error_initialize_error()`, and `GLOBUS_ERROR_TYPE_GLOBUS`.

5.11.3.3 `globus_object_t* globus_error_initialize_error (globus_object_t * error, globus_module_descriptor_t * base_source, globus_object_t * base_cause, int type, const char * source_file, const char * source_func, int source_line, const char * short_desc_format, va_list ap)`

Initialize a previously allocated error of type GLOBUS_ERROR_TYPE_GLOBUS.

Parameters:

error The previously allocated error object.

base_source Pointer to the originating module.

base_cause The error object causing the error. If this is the original error this parameter may be NULL.

type The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.

source_file Name of file. Use `__FILE__`

source_func Name of function. Use `_globus_func_name` and declare your func with `GlobusFuncName(<name>)`

source_line Line number. Use `__LINE__`

short_desc_format Short format string giving a succinct description of the error. To be passed on to the user.

ap Arguments for the format string.

Returns:

The resulting error object. You may have to call `globus_error_put()` on this object before passing it on.

References GLOBUS_ERROR_TYPE_GLOBUS.

5.12 Error Data Accessors and Modifiers

Get and set data in a Globus Generic Error object.

Collaboration diagram for Error Data Accessors and Modifiers:



Get Source

- `globus_module_descriptor_t * globus_error_get_source (globus_object_t *error)`

Set Source

- `void globus_error_set_source (globus_object_t *error, globus_module_descriptor_t *source_module)`

Get Cause

- `globus_object_t * globus_error_get_cause (globus_object_t *error)`

Set Cause

- void [globus_error_set_cause](#) (globus_object_t *error, globus_object_t *causal_error)

Get Type

- int [globus_error_get_type](#) (globus_object_t *error)

Set Type

- void [globus_error_set_type](#) (globus_object_t *error, const int type)

Get Short Description

- char * [globus_error_get_short_desc](#) (globus_object_t *error)

Set Short Description

- void [globus_error_set_short_desc](#) (globus_object_t *error, const char *short_desc_format,...)

Get Long Description

- char * [globus_error_get_long_desc](#) (globus_object_t *error)

Set Long Description

- void [globus_error_set_long_desc](#) (globus_object_t *error, const char *long_desc_format,...)

5.12.1 Detailed Description

Get and set data in a Globus Generic Error object.

This section defines operations for accessing and modifying data in a Globus Generic Error object.

5.12.2 Function Documentation

5.12.2.1 globus_module_descriptor_t* globus_error_get_source (globus_object_t * *error*)

Retrieve the originating module descriptor from a error object.

Parameters:

error The error from which to retrieve the module descriptor

Returns:

The originating module descriptor.

5.12.2.2 void globus_error_set_source (globus_object_t * *error*, globus_module_descriptor_t * *source_module*)

Set the originating module descriptor in a error object.

Parameters:

error The error object for which to set the causative error

source_module The originating module descriptor

Returns:

void

5.12.2.3 globus_object_t* globus_error_get_cause (globus_object_t * *error*)

Retrieve the underlying error from a error object.

Parameters:

error The error from which to retrieve the causative error.

Returns:

The underlying error object if it exists, NULL if it doesn't.

5.12.2.4 void globus_error_set_cause (globus_object_t * *error*, globus_object_t * *causal_error*)

Set the causative error in a error object.

Parameters:

error The error object for which to set the causative error.

causal_error The causative error.

Returns:

void

5.12.2.5 int globus_error_get_type (globus_object_t * *error*)

Retrieve the error type from a generic globus error object.

Parameters:

error The error from which to retrieve the error type

Returns:

The error type of the object

References GLOBUS_ERROR_TYPE_GLOBUS.

5.12.2.6 void globus_error_set_type (globus_object_t * *error*, const int *type*)

Set the error type in a generic globus error object.

Parameters:

error The error object for which to set the error type

type The error type

Returns:

void

References GLOBUS_ERROR_TYPE_GLOBUS.

5.12.2.7 char* globus_error_get_short_desc (globus_object_t * *error*)

Retrieve the short error description from a generic globus error object.

Parameters:

error The error from which to retrieve the description

Returns:

The short error description of the object

References GLOBUS_ERROR_TYPE_GLOBUS.

5.12.2.8 void globus_error_set_short_desc (globus_object_t * *error*, const char * *short_desc_format*, ...)

Set the short error description in a generic globus error object.

Parameters:

error The error object for which to set the description

short_desc_format Short format string giving a succinct description of the error. To be passed on to the user.

... Arguments for the format string.

Returns:

void

References GLOBUS_ERROR_TYPE_GLOBUS.

5.12.2.9 char* globus_error_get_long_desc (globus_object_t * *error*)

Retrieve the long error description from a generic globus error object.

Parameters:

error The error from which to retrieve the description

Returns:

The long error description of the object

References GLOBUS_ERROR_TYPE_GLOBUS.

5.12.2.10 void globus_error_set_long_desc (globus_object_t * *error*, const char * *long_desc_format*, ...)

Set the long error description in a generic globus error object.

Parameters:

error The error object for which to set the description

long_desc_format Longer format string giving a more detailed explanation of the error.

Returns:

void

References GLOBUS_ERROR_TYPE_GLOBUS.

5.13 Error Handling Helpers

Helper functions for dealing with Globus Generic Error objects.

Collaboration diagram for Error Handling Helpers:

**Error Match**

- globus_bool_t [globus_error_match](#) (globus_object_t **error*, globus_module_descriptor_t **module*, int type)

Print Error Chain

- char * [globus_error_print_chain](#) (globus_object_t **error*)

Print User Friendly Error Message

- char * [globus_error_print_friendly](#) (globus_object_t **error*)

5.13.1 Detailed Description

Helper functions for dealing with Globus Generic Error objects.

This section defines utility functions for dealing with Globus Generic Error objects.

5.13.2 Function Documentation

5.13.2.1 `globus_bool_t globus_error_match (globus_object_t * error, globus_module_descriptor_t * module, int type)`

Check whether the error originated from a specific module and is of a specific type.

This function checks whether the error or any of its causative errors originated from a specific module and is of a specific type. If the module descriptor is left unspecified this function will check for any error of the specified type and vice versa.

Parameters:

error The error object for which to perform the check

module The module descriptor to check for

type The type to check for

Returns:

GLOBUS_TRUE - the error matched the module and type GLOBUS_FALSE - the error failed to match the module and type

References `globus_error_get_cause()`, `globus_error_get_source()`, `globus_error_get_type()`, and `GLOBUS_ERROR_TYPE_GLOBUS`.

5.13.2.2 `char* globus_error_print_chain (globus_object_t * error)`

Return a string containing all printable errors found in a error object and its causative error chain.

If the `GLOBUS_ERROR_VERBOSE` env is set, file, line and function info will also be printed (where available). Otherwise, only the module name will be printed.

Parameters:

error The error to print

Returns:

A string containing all printable errors. This string needs to be freed by the user of this function.

References `globus_error_get_cause()`.

5.13.2.3 `char* globus_error_print_friendly (globus_object_t * error)`

Return a string containing error messages from the top 1 and bottom 3 objects, and, if found, show a friendly error message.

The error chain will be searched from top to bottom until a friendly handler is found and a friendly message is created.

If the `GLOBUS_ERROR_VERBOSE` env is set, then the result from [globus_error_print_chain\(\)](#) will be used.

Parameters:

error The error to print

Returns:

A string containing a friendly error message. This string needs to be freed by the user of this function.

References `globus_error_get_cause()`, `globus_error_get_source()`, and `globus_error_print_chain()`.

5.14 Globus Thread API

Functions

- int [globus_condattr_setspace](#) (globus_condattr_t *attr, int space)
- int [globus_condattr_getspace](#) (globus_condattr_t *attr, int *space)

5.14.1 Function Documentation

5.14.1.1 int globus_condattr_setspace (globus_condattr_t * attr, int space)

Use this function to associate a space with a cond attr.

This will allow `globus_cond_wait` to poll the appropriate space (if applicable)

A condattr's default space is `GLOBUS_CALLBACK_GLOBAL_SPACE`

Parameters:

attr attr to associate space with.

space a previously initialized space

Returns:

- 0 on success

See also:

[Globus Callback Spaces](#)

5.14.1.2 int globus_condattr_getspace (globus_condattr_t * attr, int * space)

Use this function to retrieve the space associated with a condattr.

Parameters:

attr attr to associate space with.

space storarage for the space to be passed back

Returns:

- 0 on success

See also:

[Globus Callback Spaces](#)

5.15 URL String Parser

The Globus URL functions provide a simple mechanism for parsing a URL string into a data structure, and for determining the scheme of an URL string.

Data Structures

- struct `globus_url_t`
Parsed URLs.

Enumerations

- enum `globus_url_scheme_t` {
 `GLOBUS_URL_SCHEME_FTP` = 0,
 `GLOBUS_URL_SCHEME_GSIFTP`,
 `GLOBUS_URL_SCHEME_HTTP`,
 `GLOBUS_URL_SCHEME_HTTPS`,
 `GLOBUS_URL_SCHEME_LDAP`,
 `GLOBUS_URL_SCHEME_FILE`,
 `GLOBUS_URL_SCHEME_X_NEXUS`,
 `GLOBUS_URL_SCHEME_X_GASS_CACHE`,
 `GLOBUS_URL_SCHEME_UNKNOWN` ,
 `GLOBUS_URL_NUM_SCHEMES` }

Functions

- int `globus_url_parse` (const char *url_string, `globus_url_t` *url)
- int `globus_url_parse_rfc1738` (const char *url_string, `globus_url_t` *url)
- int `globus_url_parse_loose` (const char *url_string, `globus_url_t` *url)
- int `globus_url_destroy` (`globus_url_t` *url)
- int `globus_url_get_scheme` (const char *url_string, `globus_url_scheme_t` *scheme_type)
- int `globus_url_copy` (`globus_url_t` *dst, const `globus_url_t` *src)

5.15.1 Detailed Description

The Globus URL functions provide a simple mechanism for parsing a URL string into a data structure, and for determining the scheme of an URL string.

These functions are part of the Globus common library. The `GLOBUS_COMMON` module must be activated in order to use them.

5.15.2 Enumeration Type Documentation

5.15.2.1 enum `globus_url_scheme_t`

URL Schemes.

The Globus URL library supports a set of URL schemes (protocols). This enumeration can be used to quickly dispatch a parsed URL based on a constant value.

See also:

[globus_url_t::scheme_type](#)

Enumerator:

GLOBUS_URL_SCHEME_FTP File Transfer Protocol.
GLOBUS_URL_SCHEME_GSIFTP GSI-enhanced File Transfer Protocol.
GLOBUS_URL_SCHEME_HTTP HyperText Transfer Protocol.
GLOBUS_URL_SCHEME_HTTPS Secure HyperText Transfer Protocol.
GLOBUS_URL_SCHEME_LDAP Lightweight Directory Access Protocol.
GLOBUS_URL_SCHEME_FILE File Location.
GLOBUS_URL_SCHEME_X_NEXUS Nexus endpoint.
GLOBUS_URL_SCHEME_X_GASS_CACHE GASS Cache Entry.
GLOBUS_URL_SCHEME_UNKNOWN Any other URL of the form <scheme>://<something>.
GLOBUS_URL_NUM_SCHEMES Total number of URL schemes supported.

5.15.3 Function Documentation

5.15.3.1 `int globus_url_parse (const char * url_string, globus_url_t * url)`

Parse a string containing a URL into a [globus_url_t](#).

Parameters:

url_string String to parse

url Pointer to [globus_url_t](#) to be filled with the fields of the url

Return values:

GLOBUS_SUCCESS The string was successfully parsed.
GLOBUS_URL_ERROR_NULL_STRING The *url_string* was GLOBUS_NULL.
GLOBUS_URL_ERROR_NULL_URL The URL pointer was GLOBUS_NULL.
GLOBUS_URL_ERROR_BAD_SCHEME The URL scheme (protocol) contained invalid characters.
GLOBUS_URL_ERROR_BAD_USER The user part of the URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_PASSWORD The password part of the URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_HOST The host part of the URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_PORT The port part of the URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_PATH The path part of the URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_DN -9 The DN part of an LDAP URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_ATTRIBUTES -10 The attributes part of an LDAP URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_SCOPE -11 The scope part of an LDAP URL contained invalid characters.
GLOBUS_URL_ERROR_BAD_FILTER -12 The filter part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_OUT_OF_MEMORY -13 The library was unable to allocate memory to create the the [globus_url_t](#) contents.

GLOBUS_URL_ERROR_INTERNAL_ERROR -14 Some unexpected error occurred parsing the URL.

References [globus_url_t::attributes](#), [globus_url_t::dn](#), [globus_url_t::filter](#), [globus_url_destroy\(\)](#), [GLOBUS_URL_SCHEME_FILE](#), [GLOBUS_URL_SCHEME_FTP](#), [GLOBUS_URL_SCHEME_GSIFTP](#), [GLOBUS_URL_SCHEME_HTTP](#), [GLOBUS_URL_SCHEME_HTTPS](#), [GLOBUS_URL_SCHEME_LDAP](#), [GLOBUS_URL_SCHEME_X_GASS_CACHE](#), [GLOBUS_URL_SCHEME_X_NEXUS](#), [globus_url_t::host](#), [globus_url_t::password](#), [globus_url_t::port](#), [globus_url_t::scheme](#), [globus_url_t::scheme_type](#), [globus_url_t::scope](#), [globus_url_t::url_path](#), [globus_url_t::url_specific_part](#), and [globus_url_t::user](#).

5.15.3.2 `int globus_url_parse_rfc1738 (const char * url_string, globus_url_t * url)`

Parse a string containing a URL into a [globus_url_t](#).

Parameters:

url_string String to parse

url Pointer to [globus_url_t](#) to be filled with the fields of the url

Return values:

GLOBUS_SUCCESS The string was successfully parsed.

GLOBUS_URL_ERROR_NULL_STRING The *url_string* was [GLOBUS_NULL](#).

GLOBUS_URL_ERROR_NULL_URL The URL pointer was [GLOBUS_NULL](#).

GLOBUS_URL_ERROR_BAD_SCHEME The URL scheme (protocol) contained invalid characters.

GLOBUS_URL_ERROR_BAD_USER The user part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_PASSWORD The password part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_HOST The host part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_PORT The port part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_PATH The path part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_DN -9 The DN part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_ATTRIBUTES -10 The attributes part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_SCOPE -11 The scope part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_FILTER -12 The filter part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_OUT_OF_MEMORY -13 The library was unable to allocate memory to create the the [globus_url_t](#) contents.

GLOBUS_URL_ERROR_INTERNAL_ERROR -14 Some unexpected error occurred parsing the URL.

References [globus_url_t::attributes](#), [globus_url_t::dn](#), [globus_url_t::filter](#), [globus_url_destroy\(\)](#), [GLOBUS_URL_SCHEME_FILE](#), [GLOBUS_URL_SCHEME_FTP](#), [GLOBUS_URL_SCHEME_GSIFTP](#), [GLOBUS_URL_SCHEME_HTTP](#), [GLOBUS_URL_SCHEME_HTTPS](#), [GLOBUS_URL_SCHEME_LDAP](#), [GLOBUS_URL_SCHEME_X_GASS_CACHE](#), [GLOBUS_URL_SCHEME_X_NEXUS](#), [globus_url_t::host](#), [globus_url_t::password](#), [globus_url_t::port](#), [globus_url_t::scheme](#), [globus_url_t::scheme_type](#), [globus_url_t::scope](#), [globus_url_t::url_path](#), [globus_url_t::url_specific_part](#), and [globus_url_t::user](#).

5.15.3.3 `int globus_url_parse_loose (const char * url_string, globus_url_t * url)`

Parse a string containing a URL into a [globus_url_t](#). Looser restrictions on characters allowed in the path part of the URL.

Parameters:

url_string String to parse

url Pointer to [globus_url_t](#) to be filled with the fields of the url

Return values:

GLOBUS_SUCCESS The string was successfully parsed.

GLOBUS_URL_ERROR_NULL_STRING The *url_string* was GLOBUS_NULL.

GLOBUS_URL_ERROR_NULL_URL The URL pointer was GLOBUS_NULL.

GLOBUS_URL_ERROR_BAD_SCHEME The URL scheme (protocol) contained invalid characters.

GLOBUS_URL_ERROR_BAD_USER The user part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_PASSWORD The password part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_HOST The host part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_PORT The port part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_PATH The path part of the URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_DN -9 The DN part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_ATTRIBUTES -10 The attributes part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_SCOPE -11 The scope part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_BAD_FILTER -12 The filter part of an LDAP URL contained invalid characters.

GLOBUS_URL_ERROR_OUT_OF_MEMORY -13 The library was unable to allocate memory to create the the [globus_url_t](#) contents.

GLOBUS_URL_ERROR_INTERNAL_ERROR -14 Some unexpected error occurred parsing the URL.

References `globus_url_t::attributes`, `globus_url_t::dn`, `globus_url_t::filter`, `globus_url_destroy()`, `GLOBUS_URL_SCHEME_FILE`, `GLOBUS_URL_SCHEME_FTP`, `GLOBUS_URL_SCHEME_GSIFTP`, `GLOBUS_URL_SCHEME_HTTP`, `GLOBUS_URL_SCHEME_HTTPS`, `GLOBUS_URL_SCHEME_LDAP`, `GLOBUS_URL_SCHEME_X_GASS_CACHE`, `GLOBUS_URL_SCHEME_X_NEXUS`, `globus_url_t::host`, `globus_url_t::password`, `globus_url_t::port`, `globus_url_t::scheme`, `globus_url_t::scheme_type`, `globus_url_t::scope`, `globus_url_t::url_path`, `globus_url_t::url_specific_part`, and `globus_url_t::user`.

5.15.3.4 `int globus_url_destroy (globus_url_t * url)`

Destroy a [globus_url_t](#) structure.

This function frees all memory associated with a [globus_url_t](#) structure.

Parameters:

url The url structure to destroy

Return values:

GLOBUS_SUCCESS The URL was successfully destroyed.

References `globus_url_t::attributes`, `globus_url_t::dn`, `globus_url_t::filter`, `globus_url_t::host`, `globus_url_t::password`, `globus_url_t::scheme`, `globus_url_t::scope`, `globus_url_t::url_path`, `globus_url_t::url_specific_part`, and `globus_url_t::user`.

5.15.3.5 `int globus_url_get_scheme (const char * url_string, globus_url_scheme_t * scheme_type)`

Get the scheme of an URL.

This function determines the scheme type of the url string, and populates the variable pointed to by second parameter with that value. This performs a less expensive parsing than `globus_url_parse()` and is suitable for applications which need only to choose a handler based on the URL scheme.

Parameters:

url_string The string containing the URL.

scheme_type A pointer to a `globus_url_scheme_t` which will be set to the scheme.

Return values:

GLOBUS_SUCCESS The URL scheme was recognized, and `scheme_type` has been updated.

GLOBUS_URL_ERROR_BAD_SCHEME The URL scheme was not recognized.

References `GLOBUS_URL_SCHEME_FILE`, `GLOBUS_URL_SCHEME_FTP`, `GLOBUS_URL_SCHEME_GSIFTP`, `GLOBUS_URL_SCHEME_HTTP`, `GLOBUS_URL_SCHEME_HTTPS`, `GLOBUS_URL_SCHEME_LDAP`, `GLOBUS_URL_SCHEME_UNKNOWN`, `GLOBUS_URL_SCHEME_X_GASS_CACHE`, and `GLOBUS_URL_SCHEME_X_NEXUS`.

5.15.3.6 `int globus_url_copy (globus_url_t * dst, const globus_url_t * src)`

Create a copy of an URL structure.

This function copies the contents of a url structure into another.

Parameters:

dst The URL structure to be populated with a copy of the contents of `src`.

src The original URL.

Return values:

GLOBUS_SUCCESS The URL was successfully copied.

GLOBUS_URL_ERROR_NULL_URL One of the URLs was `GLOBUS_NULL`.

GLOBUS_URL_ERROR_OUT_OF_MEMORY; The library was unable to allocate memory to create the `globus_url_t` contents.

References `globus_url_t::port`, `globus_url_t::scheme`, and `globus_url_t::scheme_type`.

6 Data Structure Documentation

6.1 `globus_url_t` Struct Reference

Parsed URLs.

Data Fields

- char * [scheme](#)
- [globus_url_scheme_t](#) [scheme_type](#)
- char * [user](#)
- char * [password](#)
- char * [host](#)
- unsigned short [port](#)
- char * [url_path](#)
- char * [dn](#)
- char * [attributes](#)
- char * [scope](#)
- char * [filter](#)
- char * [url_specific_part](#)

6.1.1 Detailed Description

Parsed URLs.

This structure contains the fields which were parsed from a string representation of a URL. There are no methods to access fields of this structure.

6.1.2 Field Documentation

6.1.2.1 char* globus_url_t::scheme

A string containing the URL's scheme (http, ftp, etc).

6.1.2.2 globus_url_scheme_t globus_url_t::scheme_type

An enumerated scheme type.

This is derived from the scheme string

6.1.2.3 char* globus_url_t::user

The username portion of the URL.

[ftp, gsiftp]

6.1.2.4 char* globus_url_t::password

The user's password from the URL.

[ftp, gsiftp]

6.1.2.5 char* globus_url_t::host

The host name or IP address of the URL.

[ftp, gsiftp, http, https, ldap, x-nexus]

6.1.2.6 unsigned short globus_url_t::port

The TCP port number of the service providing the URL [ftp, gsiftp, http, https, ldap, x-nexus].

6.1.2.7 char* globus_url_t::url_path

The path name of the resource on the service providing the URL.

[ftp, gsiftp, http, https]

6.1.2.8 char* globus_url_t::dn

The distinguished name for the base of an LDAP search.

[ldap]

6.1.2.9 char* globus_url_t::attributes

The list of attributes which should be returned from an LDAP search.

[ldap]

6.1.2.10 char* globus_url_t::scope

The scope of an LDAP search.

[ldap]

6.1.2.11 char* globus_url_t::filter

The filter to be applied to an LDAP search [ldap].

6.1.2.12 char* globus_url_t::url_specific_part

An unparsed string containing the remaining text after the optional host and port of an unknown URL, or the contents of a x-gass-cache URL [x-gass-cache, unknown].

7 File Documentation

7.1 globus_callback.h File Reference

Globus Callback API.

Defines

- #define [GLOBUS_CALLBACK_GLOBAL_SPACE](#)
- #define [GLOBUS_SIGNAL_INTERRUPT](#)

Convenience Macros

- #define [globus_callback_poll\(a\)](#)
- #define [globus_poll_blocking\(\)](#)
- #define [globus_poll_nonblocking\(\)](#)
- #define [globus_poll\(\)](#)
- #define [globus_signal_poll\(\)](#)
- #define [globus_callback_register_onehot\(callback_handle, delay_time, callback_func, callback_user_arg\)](#)
- #define [globus_callback_register_periodic\(callback_handle, delay_time, period, callback_func, callback_user_arg\)](#)
- #define [globus_callback_register_signal_handler\(signum, persist, callback_func, callback_user_arg\)](#)

Typedefs

Callback Prototypes

- typedef void(* [globus_callback_func_t](#))(void *user_arg)

Enumerations

- enum [globus_callback_space_behavior_t](#) {
 [GLOBUS_CALLBACK_SPACE_BEHAVIOR_SINGLE](#),
 [GLOBUS_CALLBACK_SPACE_BEHAVIOR_SERIALIZED](#),
 [GLOBUS_CALLBACK_SPACE_BEHAVIOR_THREADED](#) }

Functions

- [globus_result_t globus_callback_space_init](#) ([globus_callback_space_t](#) *space, [globus_callback_space_attr_t](#) attr)
- [globus_result_t globus_callback_space_reference](#) ([globus_callback_space_t](#) space)
- [globus_result_t globus_callback_space_destroy](#) ([globus_callback_space_t](#) space)
- [globus_result_t globus_callback_space_attr_init](#) ([globus_callback_space_attr_t](#) *attr)
- [globus_result_t globus_callback_space_attr_destroy](#) ([globus_callback_space_attr_t](#) attr)
- [globus_result_t globus_callback_space_attr_set_behavior](#) ([globus_callback_space_attr_t](#) attr, [globus_callback_space_behavior_t](#) behavior)
- [globus_result_t globus_callback_space_attr_get_behavior](#) ([globus_callback_space_attr_t](#) attr, [globus_callback_space_behavior_t](#) *behavior)
- [globus_result_t globus_callback_space_get](#) ([globus_callback_space_t](#) *space)
- [int globus_callback_space_get_depth](#) ([globus_callback_space_t](#) space)
- [globus_bool_t globus_callback_space_is_single](#) ([globus_callback_space_t](#) space)

- globus_result_t [globus_callback_space_register_signal_handler](#) (int signum, globus_bool_t persist, [globus_callback_func_t](#) callback_func, void *callback_user_arg, [globus_callback_space_t](#) space)
- globus_result_t [globus_callback_unregister_signal_handler](#) (int signum, [globus_callback_func_t](#) unregister_callback, void *unreg_arg)
- void [globus_callback_add_wakeup_handler](#) (void(*wakeup)(void *), void *user_arg)

Oneshot Callbacks

- globus_result_t [globus_callback_space_register_oneshot](#) ([globus_callback_handle_t](#) *callback_handle, const globus_reltime_t *delay_time, [globus_callback_func_t](#) callback_func, void *callback_user_arg, [globus_callback_space_t](#) space)

Periodic Callbacks

- globus_result_t [globus_callback_space_register_periodic](#) ([globus_callback_handle_t](#) *callback_handle, const globus_reltime_t *delay_time, const globus_reltime_t *period, [globus_callback_func_t](#) callback_func, void *callback_user_arg, [globus_callback_space_t](#) space)
- globus_result_t [globus_callback_unregister](#) ([globus_callback_handle_t](#) callback_handle, [globus_callback_func_t](#) unregister_callback, void *unreg_arg, globus_bool_t *active)
- globus_result_t [globus_callback_adjust_oneshot](#) ([globus_callback_handle_t](#) callback_handle, const globus_reltime_t *new_delay)
- globus_result_t [globus_callback_adjust_period](#) ([globus_callback_handle_t](#) callback_handle, const globus_reltime_t *new_period)

Callback Polling

- void [globus_callback_space_poll](#) (const globus_abstime_t *timestop, [globus_callback_space_t](#) space)
- void [globus_callback_signal_poll](#) ()

Miscellaneous

- globus_bool_t [globus_callback_get_timeout](#) (globus_reltime_t *time_left)
- globus_bool_t [globus_callback_has_time_expired](#) ()
- globus_bool_t [globus_callback_was_restarted](#) ()

Module Specific

- #define [GLOBUS_CALLBACK_MODULE](#)
- #define [GLOBUS_POLL_MODULE](#)
- enum [globus_callback_error_type_t](#) {
[GLOBUS_CALLBACK_ERROR_INVALID_CALLBACK_HANDLE](#) = 1024,
[GLOBUS_CALLBACK_ERROR_INVALID_SPACE](#),
[GLOBUS_CALLBACK_ERROR_MEMORY_ALLOC](#),
[GLOBUS_CALLBACK_ERROR_INVALID_ARGUMENT](#),
[GLOBUS_CALLBACK_ERROR_ALREADY_CANCELED](#),
[GLOBUS_CALLBACK_ERROR_NO_ACTIVE_CALLBACK](#) }
- typedef int [globus_callback_handle_t](#)
- typedef int [globus_callback_space_t](#)
- typedef struct globus_l_callback_space_attr_s * [globus_callback_space_attr_t](#)

7.1.1 Detailed Description

Globus Callback API.

Source

/home/globdev/CVS/globus-packages/common/source/library/globus_callback.h,v

Date

2006/01/19 05:54:13

Revision

1.12

Author

mblink

7.2 globus_thread_common.h File Reference

Common Thread Interface.

7.2.1 Detailed Description

Common Thread Interface.

Source

/home/globdev/CVS/globus-packages/common/source/library/globus_thread_common.h,v

Date

2006/01/19 05:54:14

Revision

1.6

Author

mblink

Index

attributes

globus_url_t, [40](#)

dn

globus_url_t, [40](#)

Error Construction, [19](#), [25](#)

Error Data Accessors and Modifiers, [21](#), [27](#)

Error Handling Helpers, [22](#), [31](#)

filter

globus_url_t, [40](#)

Globus Callback, [2](#)

Globus Callback API, [4](#)

Globus Callback Signal Handling, [17](#)

Globus Callback Spaces, [12](#)

Globus Erno Error API, [19](#)

Globus Error API, [23](#)

Globus Generic Error API, [24](#)

Globus Thread API, [33](#)

globus_callback

GLOBUS_CALLBACK_ERROR_ALREADY_-
CANCELED, [4](#)

GLOBUS_CALLBACK_ERROR_INVALID_-
ARGUMENT, [4](#)

GLOBUS_CALLBACK_ERROR_INVALID_-
CALLBACK_HANDLE, [4](#)

GLOBUS_CALLBACK_ERROR_INVALID_-
SPACE, [4](#)

GLOBUS_CALLBACK_ERROR_MEMORY_-
ALLOC, [4](#)

GLOBUS_CALLBACK_ERROR_NO_-
ACTIVE_CALLBACK, [4](#)

GLOBUS_CALLBACK_ERROR_ALREADY_-
CANCELED

globus_callback, [4](#)

GLOBUS_CALLBACK_ERROR_INVALID_-
ARGUMENT

globus_callback, [4](#)

GLOBUS_CALLBACK_ERROR_INVALID_-
CALLBACK_HANDLE

globus_callback, [4](#)

GLOBUS_CALLBACK_ERROR_INVALID_SPACE

globus_callback, [4](#)

GLOBUS_CALLBACK_ERROR_MEMORY_-
ALLOC

globus_callback, [4](#)

GLOBUS_CALLBACK_ERROR_NO_ACTIVE_-
CALLBACK

globus_callback, [4](#)

GLOBUS_CALLBACK_SPACE_BEHAVIOR_-
SERIALIZED

globus_callback_spaces, [13](#)

GLOBUS_CALLBACK_SPACE_BEHAVIOR_-
SINGLE

globus_callback_spaces, [13](#)

GLOBUS_CALLBACK_SPACE_BEHAVIOR_-
THREADED

globus_callback_spaces, [13](#)

globus_callback_spaces

GLOBUS_CALLBACK_SPACE_BEHAVIOR_-
SERIALIZED, [13](#)

GLOBUS_CALLBACK_SPACE_BEHAVIOR_-
SINGLE, [13](#)

GLOBUS_CALLBACK_SPACE_BEHAVIOR_-
THREADED, [13](#)

globus_url

GLOBUS_URL_NUM_SCHEMES, [35](#)

GLOBUS_URL_SCHEME_FILE, [35](#)

GLOBUS_URL_SCHEME_FTP, [35](#)

GLOBUS_URL_SCHEME_GSIFTP, [35](#)

GLOBUS_URL_SCHEME_HTTP, [35](#)

GLOBUS_URL_SCHEME_HTTPS, [35](#)

GLOBUS_URL_SCHEME_LDAP, [35](#)

GLOBUS_URL_SCHEME_UNKNOWN, [35](#)

GLOBUS_URL_SCHEME_X_GASS_CACHE,
[35](#)

GLOBUS_URL_SCHEME_X_NEXUS, [35](#)

GLOBUS_URL_NUM_SCHEMES

globus_url, [35](#)

GLOBUS_URL_SCHEME_FILE

globus_url, [35](#)

GLOBUS_URL_SCHEME_FTP

globus_url, [35](#)

GLOBUS_URL_SCHEME_GSIFTP

globus_url, [35](#)

GLOBUS_URL_SCHEME_HTTP

globus_url, [35](#)

GLOBUS_URL_SCHEME_HTTPS

globus_url, [35](#)

GLOBUS_URL_SCHEME_LDAP

globus_url, [35](#)

GLOBUS_URL_SCHEME_UNKNOWN

globus_url, [35](#)

GLOBUS_URL_SCHEME_X_GASS_CACHE

globus_url, [35](#)

GLOBUS_URL_SCHEME_X_NEXUS

globus_url, [35](#)

globus_callback

globus_callback_error_type_t, [3](#)

globus_callback_handle_t, [3](#)

GLOBUS_CALLBACK_MODULE, [2](#)

globus_callback_space_attr_t, [3](#)

globus_callback_space_t, [3](#)

GLOBUS_POLL_MODULE, [3](#)

- globus_callback.h, [41](#)
- globus_callback_add_wakeup_handler
 - globus_callback_signal, [18](#)
- globus_callback_adjust_oneshot
 - globus_callback_api, [9](#)
- globus_callback_adjust_period
 - globus_callback_api, [9](#)
- globus_callback_api
 - globus_callback_adjust_oneshot, [9](#)
 - globus_callback_adjust_period, [9](#)
 - globus_callback_func_t, [7](#)
 - globus_callback_get_timeout, [11](#)
 - globus_callback_has_time_expired, [11](#)
 - globus_callback_poll, [5](#)
 - globus_callback_register_oneshot, [6](#)
 - globus_callback_register_periodic, [6](#)
 - globus_callback_register_signal_handler, [6](#)
 - globus_callback_signal_poll, [10](#)
 - globus_callback_space_poll, [10](#)
 - globus_callback_space_register_oneshot, [7](#)
 - globus_callback_space_register_periodic, [8](#)
 - globus_callback_unregister, [8](#)
 - globus_callback_was_restarted, [11](#)
 - globus_poll, [5](#)
 - globus_poll_blocking, [5](#)
 - globus_poll_nonblocking, [5](#)
 - globus_signal_poll, [6](#)
- globus_callback_error_type_t
 - globus_callback, [3](#)
- globus_callback_func_t
 - globus_callback_api, [7](#)
- globus_callback_get_timeout
 - globus_callback_api, [11](#)
- GLOBAL_CALLBACK_GLOBAL_SPACE
 - globus_callback_spaces, [13](#)
- globus_callback_handle_t
 - globus_callback, [3](#)
- globus_callback_has_time_expired
 - globus_callback_api, [11](#)
- GLOBAL_CALLBACK_MODULE
 - globus_callback, [2](#)
- globus_callback_poll
 - globus_callback_api, [5](#)
- globus_callback_register_oneshot
 - globus_callback_api, [6](#)
- globus_callback_register_periodic
 - globus_callback_api, [6](#)
- globus_callback_register_signal_handler
 - globus_callback_api, [6](#)
- globus_callback_signal
 - globus_callback_add_wakeup_handler, [18](#)
 - globus_callback_space_register_signal_handler, [17](#)
 - globus_callback_unregister_signal_handler, [18](#)
 - GLOBAL_SIGNAL_INTERRUPT, [17](#)
- globus_callback_signal_poll
 - globus_callback_api, [10](#)
- globus_callback_space_attr_destroy
 - globus_callback_spaces, [15](#)
- globus_callback_space_attr_get_behavior
 - globus_callback_spaces, [15](#)
- globus_callback_space_attr_init
 - globus_callback_spaces, [14](#)
- globus_callback_space_attr_set_behavior
 - globus_callback_spaces, [15](#)
- globus_callback_space_attr_t
 - globus_callback, [3](#)
- globus_callback_space_behavior_t
 - globus_callback_spaces, [13](#)
- globus_callback_space_destroy
 - globus_callback_spaces, [14](#)
- globus_callback_space_get
 - globus_callback_spaces, [16](#)
- globus_callback_space_get_depth
 - globus_callback_spaces, [16](#)
- globus_callback_space_init
 - globus_callback_spaces, [13](#)
- globus_callback_space_is_single
 - globus_callback_spaces, [16](#)
- globus_callback_space_poll
 - globus_callback_api, [10](#)
- globus_callback_space_reference
 - globus_callback_spaces, [14](#)
- globus_callback_space_register_oneshot
 - globus_callback_api, [7](#)
- globus_callback_space_register_periodic
 - globus_callback_api, [8](#)
- globus_callback_space_register_signal_handler
 - globus_callback_signal, [17](#)
- globus_callback_space_t
 - globus_callback, [3](#)
- globus_callback_spaces
 - GLOBAL_CALLBACK_GLOBAL_SPACE, [13](#)
 - globus_callback_space_attr_destroy, [15](#)
 - globus_callback_space_attr_get_behavior, [15](#)
 - globus_callback_space_attr_init, [14](#)
 - globus_callback_space_attr_set_behavior, [15](#)
 - globus_callback_space_behavior_t, [13](#)
 - globus_callback_space_destroy, [14](#)
 - globus_callback_space_get, [16](#)
 - globus_callback_space_get_depth, [16](#)
 - globus_callback_space_init, [13](#)
 - globus_callback_space_is_single, [16](#)
 - globus_callback_space_reference, [14](#)
- globus_callback_unregister
 - globus_callback_api, [8](#)
- globus_callback_unregister_signal_handler
 - globus_callback_signal, [18](#)
- globus_callback_was_restarted
 - globus_callback_api, [11](#)
- globus_common_thread
 - globus_condattr_getspace, [33](#)

- globus_condattr_setspace, 33
- globus_condattr_getspace
 - globus_common_thread, 33
- globus_condattr_setspace
 - globus_common_thread, 33
- globus_errno_error_accessor
 - globus_error_errno_get_errno, 21
 - globus_error_errno_set_errno, 21
- globus_errno_error_object
 - globus_error_construct_errno_error, 20
 - globus_error_initialize_errno_error, 20
 - GLOBUS_ERROR_TYPE_ERRNO, 20
- globus_errno_error_utility
 - globus_error_errno_match, 22
 - globus_error_wrap_errno_error, 23
- globus_error_construct_errno_error
 - globus_errno_error_object, 20
- globus_error_construct_error
 - globus_generic_error_object, 25
- globus_error_errno_get_errno
 - globus_errno_error_accessor, 21
- globus_error_errno_match
 - globus_errno_error_utility, 22
- globus_error_errno_set_errno
 - globus_errno_error_accessor, 21
- globus_error_get_cause
 - globus_generic_error_accessor, 29
- globus_error_get_long_desc
 - globus_generic_error_accessor, 30
- globus_error_get_short_desc
 - globus_generic_error_accessor, 30
- globus_error_get_source
 - globus_generic_error_accessor, 28
- globus_error_get_type
 - globus_generic_error_accessor, 29
- globus_error_initialize_errno_error
 - globus_errno_error_object, 20
- globus_error_initialize_error
 - globus_generic_error_object, 26
- globus_error_match
 - globus_generic_error_utility, 32
- globus_error_print_chain
 - globus_generic_error_utility, 32
- globus_error_print_friendly
 - globus_generic_error_utility, 32
- globus_error_set_cause
 - globus_generic_error_accessor, 29
- globus_error_set_long_desc
 - globus_generic_error_accessor, 31
- globus_error_set_short_desc
 - globus_generic_error_accessor, 30
- globus_error_set_source
 - globus_generic_error_accessor, 28
- globus_error_set_type
 - globus_generic_error_accessor, 29
- GLOBUS_ERROR_TYPE_ERRNO

- globus_errno_error_object, 20
- GLOBUS_ERROR_TYPE_GLOBUS
 - globus_generic_error_object, 25
- globus_error_v_construct_error
 - globus_generic_error_object, 26
- globus_error_wrap_errno_error
 - globus_errno_error_utility, 23
- globus_generic_error_accessor
 - globus_error_get_cause, 29
 - globus_error_get_long_desc, 30
 - globus_error_get_short_desc, 30
 - globus_error_get_source, 28
 - globus_error_get_type, 29
 - globus_error_set_cause, 29
 - globus_error_set_long_desc, 31
 - globus_error_set_short_desc, 30
 - globus_error_set_source, 28
 - globus_error_set_type, 29
- globus_generic_error_object
 - globus_error_construct_error, 25
 - globus_error_initialize_error, 26
 - GLOBUS_ERROR_TYPE_GLOBUS, 25
 - globus_error_v_construct_error, 26
- globus_generic_error_utility
 - globus_error_match, 32
 - globus_error_print_chain, 32
 - globus_error_print_friendly, 32
- globus_poll
 - globus_callback_api, 5
- globus_poll_blocking
 - globus_callback_api, 5
- GLOBUS_POLL_MODULE
 - globus_callback, 3
- globus_poll_nonblocking
 - globus_callback_api, 5
- GLOBUS_SIGNAL_INTERRUPT
 - globus_callback_signal, 17
- globus_signal_poll
 - globus_callback_api, 6
- globus_thread_common.h, 43
- globus_url
 - globus_url_copy, 38
 - globus_url_destroy, 37
 - globus_url_get_scheme, 38
 - globus_url_parse, 35
 - globus_url_parse_loose, 36
 - globus_url_parse_rfc1738, 36
 - globus_url_scheme_t, 34
- globus_url_copy
 - globus_url, 38
- globus_url_destroy
 - globus_url, 37
- globus_url_get_scheme
 - globus_url, 38
- globus_url_parse
 - globus_url, 35

- globus_url_parse_loose
 - globus_url, [36](#)
- globus_url_parse_rfc1738
 - globus_url, [36](#)
- globus_url_scheme_t
 - globus_url, [34](#)
- globus_url_t, [38](#)
 - attributes, [40](#)
 - dn, [40](#)
 - filter, [40](#)
 - host, [39](#)
 - password, [39](#)
 - port, [40](#)
 - scheme, [39](#)
 - scheme_type, [39](#)
 - scope, [40](#)
 - url_path, [40](#)
 - url_specific_part, [40](#)
 - user, [39](#)
- host
 - globus_url_t, [39](#)
- password
 - globus_url_t, [39](#)
- port
 - globus_url_t, [40](#)
- scheme
 - globus_url_t, [39](#)
- scheme_type
 - globus_url_t, [39](#)
- scope
 - globus_url_t, [40](#)
- URL String Parser, [34](#)
- url_path
 - globus_url_t, [40](#)
- url_specific_part
 - globus_url_t, [40](#)
- user
 - globus_url_t, [39](#)