

globus gram job manager callout error

2.1

Generated by Doxygen 1.7.4

Thu Jan 26 2012 15:44:41

Contents

1	Module Index	1
1.1	Modules	1
2	Module Documentation	1
2.1	Activation	1
2.1.1	Detailed Description	1
2.1.2	Define Documentation	2
2.2	Datatypes	2
2.2.1	Enumeration Type Documentation	2

1 Module Index

1.1 Modules

Here is a list of all modules:

Activation	1
Datatypes	2

2 Module Documentation

2.1 Activation

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation.

Defines

- **#define GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE**

2.1.1 Detailed Description

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation. Before any Globus GRAM Jobmanager Callout Error API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function returns GLOBUS_SUCCESS if the Globus GRAM Jobmanager Callout Error API was successfully initialized, and you are therefore allowed to subsequently call Globus GRAM Jobmanager Callout Error API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GRAM Jobmanager Callout Error API, the following function must be called:

```
globus_module_deactivate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function should be called once for each time Globus GRAM Jobmanager Callout Error API was activated.

2.1.2 Define Documentation

2.1.2.1 #define GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE

Module descriptor.

2.2 Datatypes

Enumerations

- enum **globus_gram_jobmanager_callout_error_t** {
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS = 0,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_SYSTEM_ERROR = 1,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED = 2,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_INVALID_JOB = 3,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_BAD_EXECUTABLE = 4,
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST = 5 }

2.2.1 Enumeration Type Documentation

2.2.1.1 enum globus_gram_jobmanager_callout_error_t

GRAM Jobmanager Callout Error codes.

Enumerator:

- GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS** Credentials not accepted.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_SYSTEM_ERROR** Authorization system misconfigured.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED** Authorization denied.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_INVALID_JOB** Authorization denied - invalid job id.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_BAD_EXECUTABLE** Authorization denied - executable not allowed.
- GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST** Last marker - never used.

Index

Activation, 1

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_-
 MODULE, 1

Datatypes, 2

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 DENIED, 2

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 DENIED_BAD_EXECUTABLE, 2

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 DENIED_INVALID_JOB, 2

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 SYSTEM_ERROR, 2

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_-
 CREDS, 2

 GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_-
 LAST, 2

 globus_gram_jobmanager_callout_error_t, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 DENIED

 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 DENIED_BAD_EXECUTABLE

 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 DENIED_INVALID_JOB

 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_-
 SYSTEM_ERROR

 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS

 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_-
 LAST

 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_-
 MODULE

 Activation, 1

 globus_gram_jobmanager_callout_error_t

 Datatypes, 2